

# Sentinel LDK 8.4

## INSTALLATION GUIDE



## Revision History

Document Number 007-012163-001 Revision G, 2202-1

## Disclaimer and Copyrights

All information herein is either public information or is the property of and owned solely by Thales DIS France S.A. and/or its subsidiaries or affiliates who shall have and keep the sole right to file patent applications or any other kind of intellectual property protection in connection with such information.

Nothing herein shall be construed as implying or granting to you any rights, by license, grant or otherwise, under any intellectual and/or industrial property rights of or concerning any of Thales DIS France S.A. and any of its subsidiaries and affiliates (collectively referred to herein after as "Thales") information.

This document can be used for informational, non-commercial, internal and personal use only provided that:

- The copyright notice below, the confidentiality and proprietary legend and this full warning notice appear in all copies.
- This document shall not be posted on any network computer or broadcast in any media and no modification of any part of this document shall be made.

Use for any other purpose is expressly prohibited and may result in severe civil and criminal liabilities.

The information contained in this document is provided "AS IS" without any warranty of any kind. Unless otherwise expressly agreed in writing, Thales makes no warranty as to the value or accuracy of information contained herein. The document could include technical inaccuracies or typographical errors. Changes are periodically added to the information herein. Furthermore, Thales reserves the right to make any change or improvement in the specifications data, information, and the like described herein, at any time.

**Thales hereby disclaims all warranties and conditions with regard to the information contained herein, including all implied warranties of merchantability, fitness for a particular purpose, title and non-infringement. In no event shall Thales be liable, whether in contract, tort or otherwise, for any indirect, special or consequential damages or any damages whatsoever including but not limited to damages resulting from loss of use, data, profits, revenues, or customers, arising out of or in connection with the use or performance of information contained in this document.**

**Thales does not and shall not warrant that this product will be resistant to all possible attacks and shall not incur, and disclaims, any liability in this respect. Even if each product is compliant with current security standards in force on the date of their design, security mechanisms' resistance necessarily evolves according to the state of the art in security and notably under the emergence of new attacks. Under no circumstances, shall Thales be held liable for any third party actions and in particular in case of any successful attack against systems or equipment incorporating Thales products. Thales disclaims any liability with respect to security for direct, indirect, incidental or consequential damages that result from any use of its products. It is further stressed that independent testing and verification by the person using the product is particularly encouraged, especially in any application in which defective, incorrect or insecure functioning could result in damage to persons or property, denial of service or loss of privacy.**

Copyright © 2022 Thales Group. All rights reserved. Thales, the Thales logo and Sentinel are trademarks and service marks of Thales and/or its subsidiaries and affiliates and are registered in certain countries. All other trademarks and service marks, whether registered or not in specific countries, are the properties of their respective owners.

# CONTENTS

<b>Preface</b>	<b>5</b>
About This Guide	5
What's Included in Sentinel LDK	5
Installing Sentinel LDK	5
Configuring Sentinel LDK to Recognize Your Vendor Code	5
Installing Sentinel LDK Run-time Environment	5
Post-Installation Software Updates	6
Training	6
<b>Chapter 1: Sentinel LDK Software Package</b>	<b>7</b>
Entitlement Management Systems	7
Sentinel EMS	7
Sentinel LDK-EMS	8
Sentinel LDK Vendor Suite	8
Vendor Tools	8
Sentinel LDK APIs	9
Sentinel LDK Run-time Environment	10
<b>Chapter 2: Installing Sentinel LDK</b>	<b>11</b>
Installing Sentinel LDK with Sentinel EMS (Thales-Hosted)	11
Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher	12
Installing a Launcher for Sentinel EMS	13
Configuring Sentinel LDK to Work With Sentinel EMS	15
Installing Sentinel LDK with Sentinel LDK-EMS (Thales-Hosted)	16
Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher	16
Installing a Launcher for Sentinel LDK-EMS	18
Configuring Sentinel LDK to Work With Sentinel LDK-EMS	20
Upgrading Sentinel Vendor Suite From Earlier Versions	21
Installing Sentinel LDK with Sentinel LDK-EMS (On-Premises)	21
Installing Sentinel LDK-EMS on Your Machine	22
Installing Sentinel LDK Vendor Suite	33
Installing a Remote Launcher for Sentinel LDK-EMS	35
Configuring Sentinel LDK to Work With Sentinel LDK-EMS on Your Network	37
Upgrading From Earlier Versions	38
Sentinel LDK-EMS Network Configuration Options	42
Troubleshooting a Sentinel LDK-EMS Installation	47
<b>Chapter 3: Introducing Your Sentinel Vendor Keys to Sentinel LDK</b>	<b>52</b>
Master Wizard Functions	52
Methods of Introducing a Vendor Key	53

Remote Connection of Vendor Keys .....	54
Selecting the Version-Enforcement Option .....	54
Using the Master Wizard to Introduce a Sentinel Vendor Key .....	56
<b>Chapter 4: Installing Sentinel LDK Run-time Environment .....</b>	<b>63</b>
Installing Sentinel LDK Run-time Environment for Mac .....	63
Installing Sentinel LDK Run-time Environment .....	63
Installed Files .....	64
Modifying the Behavior of the Daemons .....	64
Installing Sentinel LDK Run-time Environment for Linux .....	66
Installing Sentinel LDK Run-time Environment .....	67
Installed Files .....	70
Uninstalling Sentinel LDK Run-time Environment .....	70
Upgrading HASP HL Key Firmware .....	71
Installing Sentinel LDK Run-time Environment for Windows .....	71
HASPUserSetup.exe Utility .....	72
haspdinst.exe Utility .....	73
Multiple Installations on a Single End User's Computer .....	74
<b>Chapter 5: Installing Software Updates .....</b>	<b>75</b>
<b>Chapter A: Modifying and Uninstalling Sentinel LDK .....</b>	<b>77</b>
Modifying the Installed Sentinel LDK Components .....	77
Uninstalling Sentinel LDK Vendor Suite .....	77
Uninstalling Sentinel LDK-EMS (On-Premises) .....	78
<b>SENTINEL LDK PRODUCT END USER LICENSE AGREEMENT .....</b>	<b>79</b>
<b>Exhibit A - Third-Party Software .....</b>	<b>85</b>
<b>Exhibit B - Third-Party Software for Sentinel LDK-EMS .....</b>	<b>120</b>

# Preface

This guide describes how to install all required components of Sentinel LDK.

## About This Guide

---

The guide contains the sections and appendixes described below.

### What's Included in Sentinel LDK

- > ["Sentinel LDK Software Package" on page 7](#)

Describes the Sentinel LDK software package.

### Installing Sentinel LDK

- > ["Installing Sentinel LDK with Sentinel EMS \(Thales-Hosted\)" on page 11](#)

For companies who subscribe to Sentinel EMS (hosted by Thales), describes how to install and configure the required Sentinel LDK components.

- > ["Installing Sentinel LDK with Sentinel LDK-EMS \(Thales-Hosted\)" on page 16](#)

For companies who subscribe to Sentinel LDK-EMS (hosted by Thales), describes how to install and configure the required Sentinel LDK components.

- > ["Installing Sentinel LDK with Sentinel LDK-EMS \(On-Premises\)" on page 21](#)

For companies who work with Sentinel LDK-EMS installed on the company network, describes how to install and configure the required Sentinel LDK components.

### Configuring Sentinel LDK to Recognize Your Vendor Code

- > ["Introducing Your Sentinel Vendor Keys to Sentinel LDK" on page 52](#)

Describes how to introduce your Sentinel Vendor keys to the Sentinel LDK system. This ensures that your applications are protected and licensed with the unique codes that have been assigned to you.

### Installing Sentinel LDK Run-time Environment

- > ["Installing Sentinel LDK Run-time Environment for Mac" on page 63](#)

Describes how to install the Sentinel LDK Run-time Environment on a machine with a Mac operating system.

> ["Installing Sentinel LDK Run-time Environment for Linux" on page 66](#)

Describes how to install the Sentinel LDK Run-time Environment on a machine with a Linux operating system.

> ["Installing Sentinel LDK Run-time Environment for Windows" on page 71](#)

Describes additional options for installing Sentinel LDK Run-time Environment.

## Post-Installation Software Updates

> ["Installing Software Updates" on page 75](#)

This section describes how the Sentinel LDK software manager checks for software updates to ensure that you are always working with the latest version of Sentinel LDK.

> ["Modifying and Uninstalling Sentinel LDK" on page 77](#)

Describes how to completely uninstall Sentinel LDK.

## Training

---

For additional information and training about Sentinel LDK implementation issues, contact [our team](#) of international consultants who can provide you with tailored training sessions on the following:

- > Integration of Sentinel LDK into your product
- > Analysis of the best protection strategy for your applications
- > Assistance in implementation of your protection and licensing models

# CHAPTER 1: Sentinel LDK Software Package

The software described in this section is hosted on Thales servers or is provided on your Sentinel LDK Installation Drive.

**NOTE FOR MAC AND LINUX** This document describes how to install Sentinel LDK on a Windows platform. To set up Sentinel LDK Vendor Tools on a Mac or Linux platform, see:

- > For Sentinel LDK with Sentinel EMS: [Sentinel LDK Getting Started Guide for Mac](#) or [Sentinel LDK Getting Started Guide for Linux](#)
- > For Sentinel LDK with Sentinel LDK-EMS (on-premises or Thales-hosted) or an alternate entitlement management system: [Sentinel LDK Getting Started Guide for Mac](#) or [Sentinel LDK Getting Started Guide for Linux](#)
- > For Sentinel LDK with an alternate entitlement management system: [Sentinel LDK Getting Started Guide for Mac](#) or [Sentinel LDK Getting Started Guide for Linux](#)

## Entitlement Management Systems

Sentinel LDK uses one of the entitlement managements systems described in this section.

### Sentinel EMS

Sentinel EMS is a back-office server application that enables you to define, produce and update Sentinel protection keys and to define and process entitlements (customer orders).

Sentinel EMS is a new, enterprise-level version entitlement management system. This improved version of Sentinel EMS provides an advanced user interface and REST API to manage resources. Sentinel EMS supports multiple methods of enforcement, including custom and third-party enforcement types. Sentinel EMS REST API enables you to integrate the entitlement and production functionality of Sentinel EMS in your own back-office management software. For details, see <https://docs.sentinel.thalesgroup.com/softwareandservices/ems/default.htm>.

You subscribe to Sentinel EMS as a service from Thales. Thales installs a dedicated instance of Sentinel EMS for your organization and sets up the Sentinel EMS database on its own servers.

The instance of Sentinel EMS can be accessed throughout your organization using web browsers. The Sentinel EMS database contains all the licensing and entitlement information for your customers.

## Sentinel LDK-EMS

Sentinel LDK-EMS is a back-office server application that enables you to define, produce and update Sentinel protection keys and to define and process entitlements (customer orders).

Sentinel LDK-EMS supports the Sentinel LDK method of enforcement. The Sentinel LDK-EMS database contains all the licensing and entitlement information for you customers. Sentinel LDK-EMS Web Services enable you to integrate the entitlement and production functionality of Sentinel LDK-EMS in your own back-office management software. For details, see <https://docs.sentinel.thalesgroup.com/ldk/ldk-ems.htm>.

Sentinel LDK-EMS is set up in one of the following manners:

- > **Sentinel LDK-EMS (Thales-hosted):** You can subscribe to Sentinel LDK-EMS as a service from Thales. In this case, Thales installs Sentinel LDK-EMS and sets up the Sentinel LDK-EMS database on its own servers.
- > **Sentinel EMS (on-premises):** You can install Sentinel LDK-EMS locally and set up the Sentinel LDK-EMS database on your own server.

In either case, the instance of Sentinel LDK-EMS can be accessed throughout your organization using web browsers. The Sentinel LDK-EMS Customer Portal can be accessed from customer sites to activate software licenses by entering Product Keys or to update licenses automatically.

**NOTE** For the Demo version of Sentinel LDK, you must install Sentinel LDK-EMS on your own server.

## Sentinel LDK Vendor Suite

The Sentinel LDK installer described in this document enables you to install Sentinel LDK Vendor Suite for use by software developers. Sentinel LDK Vendor Suite consists of the elements described below.

### Vendor Tools

Vendor Tools are used to implement protection and licensing for your applications. The most-used Sentinel LDK Vendor Tools are:

- > **Sentinel LDK Envelope**

Applies security to your software within a protective shield. Available for Windows, Mac, and Linux platforms.

- > **Sentinel LDK ToolBox**

Enables you to familiarize yourself with the Sentinel Licensing API and to generate code to include in your software's source code. Available for Windows platforms.



## Sentinel LDK APIs

The primary APIs are the following:

### > Sentinel Licensing API

Enables you to protect your application by inserting calls to a Sentinel protection key throughout your source code.

On the machine where Sentinel LDK Vendor Tools are installed, a **Sample** folder contains samples for various compilers and programming languages. Each sample includes:

- Libraries that must be linked to your application
- A sample application that demonstrates the use of the API

**Sample** folders are also provided in the Sentinel LDK directory structures for Linux and macOS.

These samples enable you to integrate protection into your own software using a variety of programming languages.

### > Sentinel Admin API

Sentinel Admin API provides the functionality available in Admin Control Center and Admin License Manager in the form of callable API functions. You can call functions to retrieve information from local or remote License Managers and to perform actions in these License Managers.

### > Sentinel License Generation API

For sites that already have a licensing infrastructure in place or that prefer to implement an alternative to Sentinel EMS or Sentinel LDK-EMS, Sentinel LDK offers a standalone licensing solution.

You can use Sentinel License Generation API together with your existing licensing server software and ERP and CRM back-office systems for maximum flexibility and control over your business processes.

Sentinel License Generation API provides the functionality required to generate and maintain Sentinel protection keys, but without any of the back-office services that are provided by Sentinel EMS or Sentinel LDK-EMS. All the required services are provided by the system that you choose to implement. You would use Sentinel LDK only to handle the protection and Feature-control functions for your applications.

#### **\*\*WARNING\*\***

**Sentinel License Generation API cannot be used in parallel with Sentinel EMS or Sentinel LDK-EMS to update licenses for a given customer.**

For links to these API references:

- > If your company subscribes to Sentinel EMS (hosted by Thales), see <https://docs.sentinel.thalesgroup.com/softwareandservices/ldk/default.htm>. (Excludes the Sentinel License Generation API, which is not applicable for this subscription.)
- > If your company works with Sentinel LDK-EMS (hosted by Thales or installed on the company network), see <https://docs.sentinel.thalesgroup.com/ldk/apis.htm>.

## Sentinel LDK Run-time Environment

---

Sentinel LDK Run-time Environment is the main link between a Sentinel protection key and a protected application or data file following its deployment at a customer's site. Depending on the type of protection key used, end users may need to have Sentinel LDK Run-time Environment installed in order to run the protected application or to access a protected data file.

You can integrate the Sentinel LDK Run-time Environment installer into the installation of your protected application.

Sentinel LDK Run-time Environment is also required by Sentinel LDK Vendor Tools and by Sentinel EMS and Sentinel LDK-EMS to update protection keys. The Sentinel LDK Installer installs the Run-time Environment on your machines when you install any of the Sentinel LDK components.

Sentinel Admin Control Center is included in the Run-time Environment. Sentinel Admin Control Center is a customizable, Web-based, vendor and end-user utility that enables centralized administration of Sentinel License Managers and Sentinel protection keys.

Use Sentinel Admin Control Center to monitor licenses and sessions when a protected application or data file is operating, to manage cloud licensing, and to manage detachable licenses.

For links to the Sentinel LDK Run-time Environment readme files:

- > If your company subscribes to Sentinel EMS (hosted by Thales), see <https://docs.sentinel.thalesgroup.com/softwareandservices/ldk/default.htm>.
- > If your company works with Sentinel LDK-EMS (hosted by Thales or installed on the company network), see <https://docs.sentinel.thalesgroup.com/ldk/rte.htm>.

## CHAPTER 2: Installing Sentinel LDK

This section describes how to install Sentinel LDK with one of the following ["Entitlement Management Systems"](#) on page 7.

> ["Installing Sentinel LDK with Sentinel EMS \(Thales-Hosted\)"](#) below

For companies who subscribe to Sentinel EMS (hosted by Thales), describes how to install and configure the required Sentinel LDK components.

> ["Installing Sentinel LDK with Sentinel LDK-EMS \(Thales-Hosted\)"](#) on page 16

For companies who subscribe to Sentinel LDK-EMS (hosted by Thales), describes how to install and configure the required Sentinel LDK components.

> ["Installing Sentinel LDK with Sentinel LDK-EMS \(On-Premises\)"](#) on page 21

For companies who work with Sentinel LDK-EMS installed on the company network, describes how to install and configure the required Sentinel LDK components.

### Installing Sentinel LDK with Sentinel EMS (Thales-Hosted)

This section is intended for vendors who want to work with Sentinel LDK and have subscribed to Sentinel EMS hosted on Thales servers.

This section describes how to install Sentinel LDK on a Windows machine, including a launcher for Sentinel EMS.

For a description of the various components that comprise Sentinel LDK, see ["Sentinel LDK Software Package"](#) on page 7.

The following procedures are described:

> ["Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher"](#) on the next page

This procedure describes how to install Sentinel LDK Vendor Suite with the Sentinel LDK launcher for starting Sentinel EMS.

> ["Installing a Launcher for Sentinel EMS"](#) on page 13

This procedure describes how to install the Sentinel LDK launcher for starting Sentinel EMS.

> ["Configuring Sentinel LDK to Work With Sentinel EMS"](#) on page 15

This procedure describes how to set the Sentinel EMS URL for integration with Sentinel LDK.


## Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher

Follow the instructions below to install Sentinel LDK Vendor Suite with a Sentinel LDK launcher for starting Sentinel EMS.

(Otherwise, if you want to install only a Sentinel LDK launcher for starting Sentinel EMS, go to ["Installing a Launcher for Sentinel EMS" on the next page.](#))

### To install Sentinel LDK Vendor Suite with a Sentinel LDK launcher:

1. Ensure that you do not have any Sentinel Vendor keys or Sentinel HL keys connected to your machine.
2. Connect the Sentinel LDK Installation Drive to your machine.
3. Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
4. Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
5. Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
6. Click **Next**. You are asked to accept the license agreement.
7. Accept the agreement and click **Next**. The Installation Options screen is displayed:




8. Ensure that the following options are selected:

- **Vendor Suite**
- **Entitlement Management System**
  - **Sentinel EMS – hosted by Thales**

Click **Next**.

**9.** Follow the instructions to install Sentinel Vendor Suite.

After the Installation Wizard has completed, Sentinel LDK Software Manager checks automatically to determine if a later version of any of the Sentinel LDK software is available. If a later version is found, a message similar to the following is displayed:



- 10.** You can click **Install** to install the update. For more information regarding this message, see ["Installing Software Updates" on page 75](#).
- 11.** When the installation process is completed: Configure the Sentinel LDK launcher to start Sentinel EMS as described in ["Configuring Sentinel LDK to Work With Sentinel EMS" on page 15](#).


## Installing a Launcher for Sentinel EMS

If you are not installing Sentinel Vendor Suite on the machine, use the procedure below to install a Sentinel LDK launcher for starting Sentinel EMS.

(Otherwise, if you want to install both Sentinel LDK Vendor Suite and a Sentinel LDK launcher for starting Sentinel EMS, go to ["Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher" on the previous page](#).)

### To install a launcher for Sentinel EMS:

- 1.** Ensure that you do not have any Sentinel Vendor keys or Sentinel HL keys connected to your machine.
- 2.** Connect the Sentinel LDK Installation Drive to your machine.
- 3.** Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
- 4.** Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
- 5.** Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
- 6.** Click **Next**. You are asked to accept the license agreement.
- 7.** Accept the agreement and click **Next**. The Installation Options screen is displayed:



8. Ensure that only the following options are selected:

- **Entitlement Management System**
  - **Sentinel EMS – hosted by Thales**

Click **Next**.

9. Follow the instructions to install the Sentinel LDK launcher.


10. When the installation process has completed: Configure the Sentinel LDK launcher to start Sentinel EMS as described in ["Configuring Sentinel LDK to Work With Sentinel EMS" below](#).


## Configuring Sentinel LDK to Work With Sentinel EMS

Follow the instructions below to configure Sentinel LDK to work with Sentinel EMS on a Windows machine.

### To configure Sentinel LDK to work with Sentinel EMS:

1. From the Start menu, select **Thales > Sentinel LDK**. The Sentinel LDK Launcher is displayed.



2. Set the Sentinel EMS URL.
  - a. In the navigation pane, next to **Sentinel EMS**, click the edit button . The Set Up Access to Sentinel EMS screen is displayed.
  - b. Enter the URL for Sentinel EMS and click **Save**.
3. Set the Sentinel EMS URL for Sentinel Admin Control Center.
  - a. From the navigation pane, click **Additional Tools > Admin Control Center**. Sentinel Admin Control Center opens.
  - b. In the Options pane, click **Configuration**. The Configuration page is displayed.

- c. From the top of the page, click the **Network** tab. The Network page is displayed.
- d. In the **EMS URL** field, add the URL for Sentinel EMS. (Do not overwrite any existing URLs in the field.)
- e. Click **Submit**.

## Installing Sentinel LDK with Sentinel LDK-EMS (Thales-Hosted)

---

This section is intended for vendors who want to work with Sentinel LDK and have subscribed to Sentinel LDK-EMS hosted on Thales servers.

The section describes how to install Sentinel LDK on a Windows machine, including a launcher for Sentinel LDK-EMS.

For a description of the various components that comprise Sentinel LDK, see ["Sentinel LDK Software Package" on page 7](#).

The following procedures are described:

> ["Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher" below](#)

This procedure describes how to install Sentinel LDK Vendor Suite with the Sentinel LDK launcher for starting Sentinel LDK-EMS.

> ["Installing a Launcher for Sentinel LDK-EMS" on page 18](#)

This procedure describes how to install the Sentinel LDK launcher for starting Sentinel LDK-EMS.

> ["Configuring Sentinel LDK to Work With Sentinel LDK-EMS" on page 20](#)

This procedure describes how to set the Sentinel LDK-EMS URL for integration with Sentinel LDK.

> ["Upgrading Sentinel Vendor Suite From Earlier Versions" on page 21](#)

This section describes how to upgrade to the latest version of Sentinel LDK from earlier versions of Sentinel LDK.

### Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher

Follow the instructions below to install Sentinel LDK Vendor Suite with a Sentinel LDK launcher for starting Sentinel LDK-EMS.


(Otherwise, if you want to install only a Sentinel LDK launcher for starting Sentinel LDK-EMS, go to ["Installing a Launcher for Sentinel EMS" on page 13](#).)

#### To install Sentinel LDK Vendor Suite with a Sentinel LDK launcher:

1. Ensure that you do not have any Sentinel Vendor keys or Sentinel HL keys connected to your machine.
2. Connect the Sentinel LDK Installation Drive to your machine.



3. Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
4. Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
5. Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
6. Click **Next**. You are asked to accept the license agreement.
7. Accept the agreement and click **Next**. The Installation Options screen is displayed:




8. Ensure that the following options are selected:
  - **Vendor Suite**
  - **Entitlement Management System**
    - **Sentinel LDK-EMS – hosted by Thales or on your network**

Click **Next**.

9. Follow the instructions to install Sentinel Vendor Suite.

After the Installation Wizard has completed, Sentinel LDK Software Manager checks automatically to determine if a later version of any of the Sentinel LDK software is available. If a later version is found, a message similar to the following is displayed:



10. You can click **Install** to install the update. For more information regarding this message, see ["Installing Software Updates" on page 75](#).
11. When the installation process is completed: Configure the Sentinel LDK launcher to start Sentinel LDK-EMS as described in ["Configuring Sentinel LDK to Work With Sentinel LDK-EMS" on page 20](#).


## Installing a Launcher for Sentinel LDK-EMS

If you are not installing Sentinel Vendor Suite on the machine, use the procedure below to install a Sentinel LDK launcher for starting Sentinel LDK-EMS.

(Otherwise, if you want to install both Sentinel LDK Vendor Suite and a Sentinel LDK launcher for starting Sentinel LDK-EMS, go to ["Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher" on page 16](#).)

### To install a launcher for Sentinel LDK-EMS:

1. Ensure that you do not have any Sentinel Vendor keys or Sentinel HL keys connected to your machine.
2. Connect the Sentinel LDK Installation Drive to your machine.
3. Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
4. Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
5. Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
6. Click **Next**. You are asked to accept the license agreement.
7. Accept the agreement and click **Next**. The Installation Options screen is displayed:



8. Ensure that only the following options are selected:

- **Entitlement Management System**
  - **Sentinel LDK-EMS – hosted by Thales or on your network**

Click **Next**.

9. Follow the instructions to install the Sentinel LDK launcher.


10. When the installation process is complete: Configure the Sentinel LDK launcher to start Sentinel LDK-EMS as described in ["Configuring Sentinel LDK to Work With Sentinel LDK-EMS" on the next page](#).


## Configuring Sentinel LDK to Work With Sentinel LDK-EMS

Follow the instructions below to configure Sentinel LDK to work with Sentinel LDK-EMS on a Windows machine.

### To configure Sentinel LDK to work with Sentinel LDK-EMS:

1. From the Start menu, select **Thales > Sentinel LDK**. The Sentinel LDK Launcher is displayed.



2. Set the Sentinel LDK-EMS URL.
  - a. In the navigation pane, next to **Sentinel LDK-EMS**, click the edit button . The Set Up Access to Sentinel LDK-EMS screen is displayed.
  - b. Enter the URL for Sentinel LDK-EMS and click **Save**.
3. Set the Sentinel LDK-EMS URL for Sentinel Admin Control Center.
  - a. From the navigation pane, click **Additional Tools > Admin Control Center**. Sentinel Admin Control Center opens.
  - b. In the Options pane, click **Configuration**. The Configuration page is displayed.
  - c. From the top of the page, click the **Network** tab. The Network page is displayed.
  - d. In the **EMS URL** field, add the URL for Sentinel LDK-EMS. (Do not overwrite any existing URLs in the field.)

- e. Click **Submit**.

## Upgrading Sentinel Vendor Suite From Earlier Versions

This section describes how to upgrade to Sentinel Vendor Suite 8.4 from an earlier version of Sentinel LDK, Sentinel HASP, or HASP SRM.

### To upgrade Sentinel Vendor Suite:

1. On each machine where you installed Vendor Suite, rerun the installation process described in ["Installing Sentinel LDK Vendor Suite" on page 33](#).
2. After completing the installation procedure on each machine, re-introduce your Developer key.

## Installing Sentinel LDK with Sentinel LDK-EMS (On-Premises)

This section is intended for vendors who want to install all components of Sentinel LDK on their local network.

These components can be installed on the same machine (for example, to experiment with the Demo Tutorial). However, in production environments, these components are typically installed on separate machines. (The Vendor Suite is often installed on multiple developers' machines.)

For a description of the various components that comprise Sentinel LDK, see ["Sentinel LDK Software Package" on page 7](#).

For information on supported platforms for Sentinel LDK, see the [Sentinel LDK Release Notes](#).

The following procedures are described:

- > ["Installing Sentinel LDK-EMS on Your Machine" on the next page](#)

This procedure describes how to install Sentinel LDK-EMS by itself or together with Sentinel LDK Vendor Suite on a single machine.

- > ["Installing Sentinel LDK Vendor Suite" on page 33](#)

This procedure describes how to install Sentinel LDK Vendor Suite with the Sentinel LDK launcher for starting Sentinel LDK-EMS.

- > ["Installing a Remote Launcher for Sentinel LDK-EMS" on page 35](#)

This procedure describes how to install a remote Sentinel LDK launcher for starting Sentinel LDK-EMS.

- > ["Configuring Sentinel LDK to Work With Sentinel LDK-EMS on Your Network" on page 37](#)

This procedure describes how to set the Sentinel LDK-EMS URL for integration with Sentinel LDK.

> ["Upgrading From Earlier Versions" on page 38](#)

This section describes how to upgrade to the latest version of Sentinel LDK from earlier versions of Sentinel LDK.

> ["Sentinel LDK-EMS Network Configuration Options" on page 42](#)

For Sentinel LDK-EMS (on-premises), describes advanced network options, including how to install the Sentinel LDK-EMS Service components on separate servers.

> ["Troubleshooting a Sentinel LDK-EMS Installation" on page 47](#)

Discusses the solutions to some of the frequently asked questions relating to the installation of the Sentinel LDK-EMS Service in a network environment.

## Installing Sentinel LDK-EMS on Your Machine

When installed on your machine, Sentinel LDK-EMS is installed under Windows as a service (referred to as the *Sentinel LDK-EMS Service*). An installation of Sentinel LDK-EMS provides the database server and all the required web services for your organization. Any authorized user in the organization can access the Sentinel LDK-EMS web interface or can use an application that employs Sentinel LDK-EMS Web Services.

To upgrade from an earlier version of Sentinel LDK-EMS, see ["Upgrading From Earlier Versions" on page 38](#).

**NOTE** Sentinel LDK-EMS can be installed on multiple computers, either to divide the workload among different machine or to ensure high availability, or both. Similarly, Sentinel LDK-EMS can be installed separately from the Sentinel LDK-EMS database.

For more information, see ["Sentinel LDK-EMS Network Configuration Options" on page 42](#).

If you experience any problems during or after Sentinel LDK-EMS installation, see ["Troubleshooting a Sentinel LDK-EMS Installation" on page 47](#).

This section lists the prerequisites for installation and provides additional information to that provided in the Installation wizard.

**In this section:**

> ["Installing and Configuring SQL Server Manually \(Optional\)" on the next page](#)

> ["Infrastructure and Prerequisites" on page 24](#)

> ["Securing Your Sentinel LDK-EMS Installation" on page 27](#)

> ["Types of Installation Setup" on page 27](#)

> ["Installing Sentinel LDK-EMS" on page 27](#)

> ["Configuring Sentinel LDK-EMS to Work With JRE" on page 32](#)

> ["Accessing Sentinel LDK-EMS" on page 32](#)

- > ["Configuring Sentinel LDK-EMS" on page 33](#)

### Installing and Configuring SQL Server Manually (Optional)

You can optionally install and configure SQL Server as a standalone operation without using the Sentinel LDK installation wizard. This is typically required:

- > When you install the Sentinel LDK-EMS database on a different machine from Sentinel LDK-EMS Service.
- > When you want to use a version of Microsoft SQL Server other than the default version. (By default, the Sentinel LDK installation wizard installs SQL Server 2019 Express.)

Download and install Microsoft SQL Server from: <https://www.microsoft.com/en-in/download/details.aspx?id=42299>

#### In this section:

- > ["Installing SQL Server" below](#)
- > ["Configuring SQL Server" on the next page](#)

### Installing SQL Server

When using the **Express** setup type to install Sentinel LDK-EMS, you have the option to first install SQL Server manually on the machine where you will install Sentinel LDK-EMS.

When using the **Advanced** setup type, an SQL Server must already exist and must be active, either on the local machine or on a different machine.

If you install SQL Server manually, you can install any of the supported versions of SQL Server.

#### To install SQL server, use one of the following methods:

- > Install the SQL Server instance using a command prompt (silent installation). For example: For SQL Server Express 2019, use:

```
SQLEXPR_x64_ENU.exe /q /IACCEPTSQLSERVERLICENSETERMS /ACTION=Install /FEATURES=SQL
/INSTANCENAME=EMSDATABASE /SAPWD=DBA!sa@EMSDb123 /SQLSVCSTARTUPTYPE=Automatic
/SECURITYMODE=SQL /SQLSVCACCOUNT="NT AUTHORITY\Network Service" /TCPENABLED=1
```

For other versions of SQL Server, the syntax of the installation command may be different.

Installation software for SQL Server Express 2019 can be found on the Sentinel LDK Installation Drive, under: `\Windows\3rdparty\MSSQLExpress2019\`

- > Install the SQL Server instance using a normal installation, and specify the following:
  - (For the **Express** setup type) Specify the instance Name as: `EMSDATABASE`
  - Select the mix mode installation. (Windows authentication and SQL Authentication)

The password for the **sa** user is as follows:

- > For the **Express** setup type: The password for the **sa** user must be: DBA!sa@EMSDb123
- > For the **Advanced** setup type: The password for the **sa** user should not contain any characters from a non-English language. (Numbers and special characters such as !, @ and # are allowed.)

## Configuring SQL Server

When you choose to install SQL Server manually for either the **Express** or **Advanced** setup type of Sentinel LDK-EMS installation, you must use the specifications described in this section.

### Enable TCP/IP

1. Open SQL Server Configuration Manager (**Start > Programs > Microsoft SQL Server 2019 > SQL Server Configuration manager**)
2. In the left pane, expand the node SQL Server 2019 Network Configuration.
3. Select Protocols for EMSDATABASE. The protocol names and their status appear in the right pane. (For the **Advanced** setup type, you can use any instance name.)
4. In the right pane, double-click **TCP/IP**. The TCP/IP Properties dialog box is displayed.
5. Under the **Protocol** tab, select **Yes** from the list against the Enabled context menu.
6. Restart the SQL Server (EMDATABAS) service.

### Configure the TCP/IP Port

1. Right-click **TCP/IP**. In the context menu, select **Properties**. The TCP/IP Properties dialog is displayed.
2. Select the **IP Addresses** tab.
3. Expand the **IPAll** node and do the following:
  - a. Set the **TCP Port** field to blank. The SQL Server Express will not automatically choose another port when it restarts.
  - b. Set the desired port number in the TCP Dynamic Port field (for example, 1433).
  - c. Click **OK**.
4. Restart the SQL Server (EMDATABAS) service.

## Infrastructure and Prerequisites

This section describes:

- > ["Infrastructure" on the next page](#)
- > ["Prerequisites" on the next page](#)
- > ["Hardware" on the next page](#)
- > ["Software" on page 26](#)
- > ["SSL Certificate" on page 26](#)



## Infrastructure

Sentinel LDK-EMS uses the following infrastructure software:

- > OpenJDK (installed by default by Sentinel LDK)

OR

Java Runtime Environment (JRE 8 Update 191)

- > Microsoft .NET Framework 3.5 and 4.0

**NOTE** Microsoft SQL Server 2019 Express Edition requires both Framework 3.5 and Framework 4.0.

If Framework 3.5 is not enabled on your machine:

- > The Installer attempts to install Framework 3.5. This requires internet connectivity.
- > An alternative method to enable Framework 3.5 on your machine is to follow the instructions provided on the Web pages that follow.

For Windows 10, 11:

<https://docs.microsoft.com/en-us/dotnet/framework/install/dotnet-35-windows>

For Windows Servers:

[https://docs.microsoft.com/en-us/windows-server/administration/server-manager/install-or-uninstall-roles-role-services-or-features#BKMK\\_arfw](https://docs.microsoft.com/en-us/windows-server/administration/server-manager/install-or-uninstall-roles-role-services-or-features#BKMK_arfw)

- > MS SQL Server 2019 Express Edition
- > Tomcat 9.0.56

These will be installed by the Sentinel LDK installation procedure.

(If you choose to install MS SQL independently, you can use any of the supported versions of MS SQL.)

## Prerequisites

Installation of Sentinel LDK-EMS requires the following:

### Hardware

- > Minimum CPU: Intel Core™ i5 (latest generation or higher iX generation ) Dual Core  
Recommended CPU: Intel Core™ i5 (latest generation or higher iX generation ) Quad Core
- > Minimum recommended RAM for Sentinel LDK-EMS production server: 16 GB  
Minimum recommended RAM for development, SDK evaluation: 8 GB
- > Minimum disk space: 25 GB

Thales highly recommends that you install your production Sentinel LDK-EMS server on a dedicated machine.

The URL on which Sentinel LDK-EMS will be hosted should contain only characters that satisfy the RFC 952 standard (that is: A-Z, 0-9, minus sign and period).

**NOTE** Sentinel LDK-EMS Service must be installed on a machine whose computer name does not exceed 15 characters.

## Software

For the list of supported operating systems, refer to the [Sentinel LDK Release Notes](#).

## SSL Certificate

Sentinel LDK-EMS can be configured to use either the HTTP or HTTPS protocol for communication between the Sentinel LDK-EMS web server and the web browsers used to access Sentinel LDK-EMS.

The HTTPS protocol encrypts the communication between the server and web browsers. However:

- > When Sentinel LDK-EMS is configured to use HTTPS, you must use a 32-bit version of Internet Explorer (version 10 or version 11) for any action that accesses a protection key (such as burn, recycle, check in key, check in c2v, or online activation).

With HTTPS, functions such as Check in Key, Check in C2V, and Recycle Keys continue to be accessed with the help of Java-based applets. Each time you access one of these functions, an applet window opens to provide the required functionality.

- > The communication with HTTPS is somewhat slower than with HTTP.
- > To work with HTTPS, you may want to purchase an SSL (Secure Sockets Layer) certificate from a certificate authority. An SSL certificate is a digital certificate that authenticates the identity of a web site to visiting web browsers and encrypts information for the server using SSL technology. (The Sentinel LDK-EMS installation process automatically generates an SSL certificate. However, each user's web browser will generate a security exception with this certificate each time the user logs in.)

To install an SSL certificate that you obtained from a certificate authority, see the [Sentinel LDK-EMS Configuration Guide](#) (described in "Configuring Sentinel LDK-EMS" on page 33).

By default, Sentinel LDK-EMS is configured during installation to use HTTP. You can change this setting during installation or afterwards to use HTTPS. To change this setting after Sentinel LDK-EMS has been installed, see ["Configuring Sentinel LDK-EMS" on page 33](#).

For more information on HTTPS and SSL certificates, you can access the web sites listed below. (These links were valid when this guide was released.)

- > <http://info.ssl.com/article.aspx?id=10694>
- > <https://www.thawte.com/resources/ssl-information-center/get-started-with-ssl/index.html>
- > <http://www.verisign.com/ssl/buy-ssl-certificates/index.html>
- > [http://en.wikipedia.org/wiki/Certificate\\_authority](http://en.wikipedia.org/wiki/Certificate_authority)

## Securing Your Sentinel LDK-EMS Installation

Among the actions taken to secure your installation of Sentinel LDK-EMS, Thales recommends that you include the following:

- > Use a strong password for logging in to Sentinel LDK-EMS, and change the password periodically.
- > Deploy a WAF (web application firewall) in front of Sentinel LDK-EMS.
- > The Microsoft SQL Server connection to the Sentinel LDK-EMS database should be enabled with HTTPS.
- > Use the latest version of TLS to secure communication with Sentinel LDK-EMS.

## Types of Installation Setup

The Sentinel LDK-EMS installation wizard offers two types of installation setup:

### Express

This setup type searches for the Sentinel LDK-EMS database and SQL Server on the local machine. If they are present, the installation wizard connects automatically to the database. If they are not present, the installation wizard installs the Sentinel LDK-EMS database and SQL Server automatically on the local machine.

No configuration screens are displayed during the installation process. If SQL Server is installed by the wizard, the SQL Server instance has the following user name and password:

- > User Name: **sa**
- > Password: **DBA!sa@EMSDB123**

### Advanced

For this setup type, an SQL Server must already exist and must be active, either on the local machine or on a different machine. The installation wizard can either create a new Sentinel LDK-EMS database schema in SQL Server, or it can connect to an existing Sentinel LDK-EMS database.

With this setup type, you can also choose where to install Sentinel LDK-EMS and whether to use SSL security for Sentinel LDK-EMS web access.

**NOTE** To create the Sentinel LDK-EMS database yourself, see "[Installing and Configuring SQL Server Manually \(Optional\)](#)" on page 23.

## Installing Sentinel LDK-EMS


You use the Sentinel LDK installation wizard from the Sentinel LDK Installation Drive to install Sentinel LDK-EMS. The installation wizard enables you to create a default installation with a basic configuration.

**To run the Sentinel LDK Installation Wizard:**

1. Log in to an account that has full administrator rights on the machine.
2. Close all open applications (including web browsers) on the machine where you will install Sentinel LDK-EMS.

**NOTE** Before starting the Sentinel LDK Installation Wizard, ensure that no Windows update installation or any other **msi** installation is in progress.


3. Connect the Sentinel LDK Installation Drive to your machine.
4. Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
5. Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
6. Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
7. Click **Next**. You are asked to accept the license agreement. Read the license agreement carefully.
8. Accept the agreement and click **Next**. The Installation Options screen is displayed:



9. In the Installation Options screen, ensure that the following options are selected:
  - **Vendor Suite** (Select only if you are also installing Vendor Suite on the same machine.)

- **Entitlement Management System**
  - **Sentinel LDK-EMS** – install on this machine

10. Click **Next**. The Setup Type screen is displayed:



11. In the Setup Type screen, select one of the following:

- **Express.** The installation wizard complete the installation of Sentinel LDK-EMS using the defaults described earlier. A minimal amount of additional user input is required.  
  
If you selected the check box for Sentinel Vendor Suite, then Sentinel LDK Vendor Suite is also installed.
- **Advanced.** The installation wizard will prompt you for information on setting up the Sentinel LDK-EMS database and SSL security. (Ensure that Microsoft SQL Server for the database is active when you run the installation wizard.)

For more information, see ["Types of Installation Setup" on page 27](#).

12. Click **Next**. The Destination Folder screen is displayed. If you want, change the destination folder for Sentinel LDK.

13. Click **Install**. Installation proceeds. This requires several minutes. Accept all defaults during installation.

14. If you selected the **Express** setup type, continue with [Step 16](#).


Otherwise, the Database Server Details screen is displayed.

**15.** In the Database Server Details screen, enter the details for the existing SQL Server instance that will be used for the Sentinel LDK-EMS database. Then, in the Database Details area, select one of the following options:

- **Existing database.** The installation wizard configures Sentinel LDK-EMS to use the existing Sentinel LDK-EMS database whose details you specified.
- **New database.** The installation wizard creates a new Sentinel LDK-EMS database in the SQL Server instance that you specified above.

When you create a new database, you can select or clear the option **Fill Demo Data**. (The option is selected by default.) If the option is selected, the installation wizard adds demo information for the DEMOMA Batch Code to the Sentinel LDK-EMS database. Each Sentinel LDK-EMS user that is assigned the DEMOMA Batch Code can view and generate reports based on the demo information.

**16.** Click **Next**. The LDK-EMS Host Configuration screen is displayed.




**17.** In the LDK-EMS Host Configuration screen, you can:

- Select the **Use SSL** check box if you want to use the HTTPS protocol. To use the HTTP protocol, leave the check box clear.
- Change the HTTP port for accessing Sentinel LDK-EMS.

**18.** Click **Next**. Installation of Sentinel LDK-EMS continues to completion.

**19.** After the installation, Sentinel LDK Software Manager checks automatically to determine if a later version of any of the Sentinel LDK software is available. If a later version is found, a message similar to the following is displayed:



You can click **Install** to install the update. For more information regarding this message, see ["Installing Software Updates" on page 75](#).

20. When the entire installation process is completed, connect the Sentinel Master key to the machine on which the Sentinel LDK-EMS Service is installed.

**NOTE** If you need to re-install Sentinel LDK-EMS for any reason, you must first remove the existing Sentinel LDK-EMS program.

Removing Sentinel LDK-EMS *does not* delete the existing database.

### Configuring Sentinel LDK-EMS to Work With JRE

After installation or upgrade, Sentinel LDK-EMS works with OpenJDK. If you want to work with JRE, follow the steps below.

#### To configure Sentinel LDK-EMS to work with JRE:

1. Set the JRE\_HOME system variable to point to the path of the of an x64 JRE installation.

To check system variables, go to **Control Panel > System > Advanced > Environment Variables**.

2. After modifying JRE\_HOME, reboot the machine. Sentinel LDK-EMS now works with JRE.

### Accessing Sentinel LDK-EMS

After you install Sentinel LDK-EMS, you can log in to the default administrator account. The user name and password for the default administrator are **admin**.

**NOTE** The first time you log in to Sentinel LDK-EMS, you must change the default password for the **admin** account. You can also change this password at any time from the top-right corner of Sentinel LDK-EMS.

#### To open Sentinel LDK-EMS:

1. **Prerequisite:** Under Windows Services, start **Sentinel LDK-EMS Service** on the machine where Sentinel LDK-EMS Service is installed if the service is not already started.
2. From the Start menu, open **Sentinel LDK**. The Sentinel LDK Launcher is displayed. You can access most of the Vendor Suite applications from this screen.
3. In Sentinel LDK Launcher, click **Sentinel LDK-EMS**. If needed, configure the Sentinel LDK-EMS location as described in ["Configuring Sentinel LDK to Work With Sentinel LDK-EMS" on page 20](#).



## Configuring Sentinel LDK-EMS

You can configure Sentinel LDK-EMS from the Sentinel LDK-EMS Administration Console. Among the facilities that you may want to configure for Sentinel LDK-EMS are:

- > SMTP mail server to be used by Sentinel LDK-EMS to send various types of email notifications.
- > Configuring Sentinel LDK-EMS to use the HTTPS protocol (if this was not done during installation of Sentinel LDK-EMS).
- > Configuring license and certificate settings.

These and many other topics are described in the Sentinel LDK-EMS Configuration Guide (described below).

### To access the Sentinel LDK-EMS Administration Console:

1. Log in to Sentinel LDK-EMS as the default administrator (**admin**) or as a user with the **Super User** or the **Batch Code Admin** role.
2. Select **Administration > Administration Console**. The Sentinel LDK-EMS Administration console is displayed.

### To access the Sentinel LDK-EMS Administration Console documentation (Sentinel LDK-EMS Configuration Guide):

Do any of the following:

- > Access the online version of the [Sentinel LDK-EMS Configuration Guide](#).
- > In Sentinel LDK-EMS Administration Console, click the **Help** link at the top-right corner of the page.
- > Open the local, PDF version of the Sentinel LDK-EMS Configuration Guide:
  - a. From the Start button, enter **Sentinel LDK**. The Sentinel LDK Launcher is displayed.
  - b. Select **Documentation > Manuals and Tutorials** and navigate to **Sentinel LDK-EMS > Sentinel LDK-EMS Configuration Guide**.


## Installing Sentinel LDK Vendor Suite

Use the procedure below to install Sentinel LDK Vendor Tools on your machine without installing Sentinel LDK-EMS.

### To install Sentinel LDK Vendor Suite with a Sentinel LDK launcher:


1. Ensure that you do not have any Sentinel Vendor keys or Sentinel HL keys connected to your machine.
2. Connect the Sentinel LDK Installation Drive to your machine.

3. Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
4. Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
5. Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
6. Click **Next**. You are asked to accept the license agreement.
7. Accept the agreement and click **Next**. The Installation Options screen is displayed:



8. Ensure that the following option is selected:
  - **Vendor Suite**
 Click **Next**.
9. Follow the instructions to install Sentinel Vendor Suite.

After the Installation Wizard has completed, Sentinel LDK Software Manager checks automatically to determine if a later version of any of the Sentinel LDK software is available. If a later version is found, a message similar to the following is displayed:



10. You can click **Install** to install the update. For more information regarding this message, see ["Installing Software Updates" on page 75](#).
11. If Sentinel LDK-EMS is installed on your network (not on this machine), set the Sentinel LDK-EMS URL, as described in ["Configuring Sentinel LDK-EMS" on page 33](#).


## Installing a Remote Launcher for Sentinel LDK-EMS

If you are not installing Sentinel Vendor Suite on the machine, use the procedure below to install a Sentinel LDK launcher for starting Sentinel LDK-EMS.

(Otherwise, if you want to install both Sentinel LDK Vendor Suite and a Sentinel LDK launcher for starting Sentinel LDK-EMS, go to ["Installing Sentinel LDK Vendor Suite with Sentinel LDK Launcher" on page 16](#).)

### To install a launcher for Sentinel LDK-EMS:

1. Ensure that you do not have any Sentinel Vendor keys or Sentinel HL keys connected to your machine.
2. Connect the Sentinel LDK Installation Drive to your machine.
3. Depending on how your computer is set up, a dialog box may be displayed. If it does, select **Open folder to view files**.
4. Browse to the **Windows** folder on the Sentinel LDK Installation Drive. Double-click **setup.exe**.
5. Click **Start the Sentinel LDK Setup**. The Sentinel LDK Installation Wizard welcome window is displayed.
6. Click **Next**. You are asked to accept the license agreement.
7. Accept the agreement and click **Next**. The Installation Options screen is displayed:



8. Ensure that only the following options are selected:

- **Entitlement Management System**
  - **Sentinel LDK-EMS – hosted by Thales or on your network**

Click **Next**.

9. Follow the instructions to install the Sentinel LDK launcher.


10. When the installation process is completed: Configure the Sentinel LDK launcher to start Sentinel LDK-EMS as described in ["Configuring Sentinel LDK to Work With Sentinel LDK-EMS on Your Network" on the next page](#).


## Configuring Sentinel LDK to Work With Sentinel LDK-EMS on Your Network

Follow the instructions below to configure Sentinel LDK to work with Sentinel LDK-EMS on a Windows machine.

### To configure Sentinel LDK to work with Sentinel LDK-EMS:

1. From the Start menu, select **Thales > Sentinel LDK**. The Sentinel LDK Launcher is displayed.



2. Set the Sentinel LDK-EMS URL.
  - a. In the navigation pane, next to **Sentinel LDK-EMS**, click the edit button . The Set Up Access to Sentinel LDK-EMS screen is displayed.
  - b. Enter the URL for Sentinel LDK-EMS and click **Save**.
3. Set the Sentinel LDK-EMS URL for Sentinel Admin Control Center.
  - a. From the navigation pane, click **Additional Tools > Admin Control Center**. Sentinel Admin Control Center opens.
  - b. In the Options pane, click **Configuration**. The Configuration page is displayed.
  - c. From the top of the page, click the **Network** tab. The Network page is displayed.
  - d. In the **EMS URL** field, add the URL for Sentinel LDK-EMS. (Do not overwrite any existing URLs in the field.)

- e. Click **Submit**.

## Upgrading From Earlier Versions

This section describes how to upgrade to Sentinel LDK 8.4 from an earlier version of Sentinel LDK, Sentinel HASP or HASP SRM.

### Upgrade considerations:

- > When upgrading from Sentinel LDK versions 7.3 through 7.8 to Sentinel LDK 8.4, all non-English locales of Customer contacts and Channel Partner contacts in Sentinel LDK-EMS are converted to the English locale. A solution for this issue is provided in the technical note available [here](#).

**NOTE** You can ignore this issue if all of your Customer contacts and Channel Partner Contacts are set up to use the English locale or if you are not upgrading Sentinel LDK-EMS.

- > The procedure for upgrading to Sentinel LDK v.8.4 has only been tested for Sentinel LDK versions 8.0 and later.

If you plan to upgrade from an earlier version of Sentinel LDK, please contact Technical Support to validate the upgrade scenario. (This applies whether you are upgrading Sentinel LDK Vendor Suite, Sentinel LDK-EMS, or both.)

- > After you complete an upgrade of Sentinel LDK-EMS, the file **server.xml** includes only TLS version 1.2 as the acceptable cryptographic protocol. This version of TLS is more secure than earlier versions.

If you included TLS version 1.0 or 1.1 as an acceptable protocol until now and you want to retain that version, you must modify **server.xml** manually.

**NOTE** The TLS 1.0 and 1.1 cryptographic protocols have known vulnerabilities. Thales highly recommends that you not add TLS 1.0 or 1.1 as an acceptable protocol.

For more information, see ["Retaining TLS 1.0 or 1.1 as an Acceptable Protocol" on page 41](#).

### In this section:

- > ["Upgrading From Sentinel LDK v.6.x or Later" below](#)
- > ["Retaining TLS 1.0 or 1.1 as an Acceptable Protocol" on page 41](#)

## Upgrading From Sentinel LDK v.6.x or Later

If Sentinel LDK-EMS or Sentinel Vendor Suite from Sentinel LDK v.6.x or later has been installed on your machine, use the procedures below to upgrade to Sentinel LDK v.8.4.

### In this section:

- > ["Upgrading Vendor Suite" on the next page](#)
- > ["Upgrading Sentinel LDK-EMS" on the next page](#)

- > ["Modifying the Sentinel LDK-EMS Database for Advanced Channel Partner Functionality" below](#)
- > ["Resolving Sentinel LDK-EMS Upgrade Issues" on the next page](#)

## Upgrading Vendor Suite

No special action is required to upgrade from any earlier version of the Vendor Suite. The Sentinel LDK installation wizard automatically uninstalls and reinstalls Vendor Suite.

## Upgrading Sentinel LDK-EMS

**To upgrade from Sentinel LDK-EMS v.6.x or later:**

1. Back up the Sentinel LDK-EMS database.
2. Install Sentinel LDK-EMS as described in this section. The installation wizard automatically detects the existence of an earlier version of Sentinel LDK-EMS and offers you the option to upgrade to the latest version.

**NOTE** Thales recommends that you clear your web browser cache before you start working with the current version of Sentinel LDK-EMS.

3. Re-introduce your Master key or Developer key as described in ["Using the Master Wizard to Introduce a Sentinel Vendor Key" on page 56](#).
4. (Optional) Sentinel LDK-EMS works with OpenJDK. If you want to use JRE, continue to ["Configuring Sentinel LDK-EMS to Work With JRE" on page 32](#) to set the JRE\_HOME system variable to point to the path of the installed JRE.

## Modifying the Sentinel LDK-EMS Database for Advanced Channel Partner Functionality

This topic is relevant if you have recently added or plan to add the Channel Partner module for your Sentinel LDK Master license.

**NOTE** If you have not created any channel partners in Sentinel LDK-EMS, no special actions are required before you add the Channel Partner module. You can ignore this topic.

Until you add the Channel Partner module to your Sentinel LDK Master license, Sentinel LDK-EMS allows you to associate the entitlements for a given customer with different channel partners. Once the Channel Partner module is added, each customer can only be associated with a single channel partner.

Before you can work effectively with the advanced Channel Partner functionality provided by the module, a script must be run that modifies the Sentinel LDK-EMS database to create direct links between existing channel partners and their customers. The script ensures that no customers are associated with multiple channel partners. If a customer is associated with multiple channel partners, the script links the customer to only one of the channel partners. A log file lists the customers for whom multiple channel partners were found.

You must work with your channel partners to resolve these conflicts and ensure that each customer is connected to a single channel partner. If necessary, resolve conflicts by creating new customers in Sentinel LDK-EMS.

The script to modify the Sentinel LDK-EMS database is executed using the following methods:

- > During the Sentinel LDK-EMS upgrade procedure, the Installer automatically executes the script. Any conflicts that are found are recorded in the Installer log at `%SystemDrive%\EMS_Log\emsInstaller.log`.
- > Click the **Sync Data for Channel Partner Module** button in the Sentinel LDK-EMS Administration Portal to run the script. Any conflicts that are found are recorded in the configuration log at `%ProgramFiles (x86)\Thales\Sentinel EMS\EMSServer\webapps\ems\log\emsConfig.log`.

The script can be executed multiple times.

You can add the Channel Partner module to your Sentinel LDK Master license before or after the script is executed. However, you should plan to add the module to your LDK Master license as close as possible to the time when the script is executed (using either method).

## Resolving Sentinel LDK-EMS Upgrade Issues

**NOTE** This topic is applicable when you upgrade from Sentinel LDK-EMS v.6.3 or later to v.8.4.

The Sentinel LDK-EMS installation procedure automatically merges components that you have customized in Sentinel LDK-EMS. In addition, all configuration changes that you performed in the existing Sentinel LDK-EMS are backed up under `%EMS_HOME%\Backup`. If you find any differences after you upgrade to Sentinel LDK-EMS v.8.4, you can manually merge the conflicting files.

To resolve any differences that you may find after upgrade, you can map the backup and current locations to manually merge the files. The following table provides the details of the components that are placed in the backup location.

Customizable Component	Backup Location <code>%EMS_HOME%\Backup\...</code>	Original Location <code>%EMS_HOME%\EMSServer\webapps\...</code>
<b>Template Files (TPLs)</b>		
.TPL files	WEB-INF\classes	ems\WEB-INF\classes
<b>Themes and Languages</b>		
Themes	themes	ems\themes
Images	themes\blackGolden\images	ems\themes\blackGolden\images



Customizable Component	Backup Location %EMS_HOME%\Backup\...	Original Location %EMS_HOME%\EMSServer\ webapps\...
Language (messages_ [language_code].properties)	WEB-INF\classes	ems\WEB-INF\classes
<b>Samples</b>		
emsWSDemo	emsWSDemo	emsWSDemo
<b>Others</b>		
ems.properties	WEB-INF\classes	ems\WEB-INF\classes
message.properties	WEB-INF\classes	ems\WEB-INF\classes

### Retaining TLS 1.0 or 1.1 as an Acceptable Protocol

After you complete a new installation or upgrade of Sentinel LDK-EMS, the file **server.xml** includes only TLS version 1.2 as the acceptable cryptographic protocol. This version of TLS is more secure than earlier versions.

If, for any reason, you want to include TLS version 1.0 or 1.1 as an acceptable protocol, you must modify **server.xml** manually as described below.

**NOTE** The TLS 1.0 and 1.1 cryptographic protocols have known vulnerabilities. Thales highly recommends that you not add TLS 1.0 or 1.1 as an acceptable protocol.

#### To retain TLS 1.0 or TLS 1.1 as acceptable protocols in server.xml:

1. On the machine where Sentinel LDK-EMS is installed, open the following file in a text editor:

```
%ProgramFiles(x86)%\Thales\Sentinel EMS\EMSServer\conf\server.xml
```

2. Locate the following string in the **Connector** tag:

```
sslEnabledProtocols ="TLSv1.2"
```

3. Add TLSv1 or TLSv1.1 (or both) to the string. For example:

```
sslEnabledProtocols ="TLSv1+TLSv1.1+TLSv1.2"
```

4. Save the file.
5. In the Services window, stop and then restart **Sentinel LDK-EMS Service**.

**NOTE** The existing Activation API sample (under `\Samples\Activation\`) must be rebuilt using the latest activation libraries in order to connect to Sentinel LDK-EMS with TLS 1.0.

The latest activation libraries can be found where Sentinel LDK is installed, in these locations:

- > Windows: `%ProgramFiles(x86)%\Thales\Sentinel LDK\Legacy\API\Activation\C\`
- > Linux: `Linux\Legacy\API\Activation\C\`
- > Mac: `MacOS\Legacy\API\Activation\C\`

## Sentinel LDK-EMS Network Configuration Options

Sentinel LDK-EMS is a web-based, multi-tier application with two primary components: Sentinel LDK-EMS Service and the Sentinel LDK-EMS database. These components can be installed on a single machine or on separate machines (server).

The web application front end in Sentinel LDK-EMS Service provides two portals, one for software vendor users and another for customers (primarily for activation purposes). Sentinel LDK-EMS Service can be installed and configured for each portal on a separate machine. (This is not a typical configuration for web applications.)

Based on the vendor requirements, a number of security provisions are possible for Sentinel LDK-EMS installation. Instances of Sentinel LDK-EMS are usually installed on a DMZ (demilitarized zone) using an external firewall that controls external access, and an internal firewall that allows access to the Sentinel LDK-EMS database.

Sentinel LDK-EMS listens on a TCP port for incoming requests. If the installation is configured for SSL, the requests are encrypted using the built-in SSL feature. Sentinel LDK-EMS then communicates with the Sentinel LDK-EMS database (a single database for the entire system) to process the requests.

This section describes the considerations and procedures for installing the Sentinel LDK-EMS components, including different configurations for installing Sentinel LDK-EMS on multiple machines in a network environment.

**NOTE** Thales recommends that you:

- > Frequently back up your Sentinel LDK-EMS database to protect your data.
- > Add adequate security measure including SSL communication link and a firewall to protect your data and application.

### In this section:

- > ["Standard Production Configuration for Sentinel LDK-EMS" on the next page](#)

Installation of Sentinel LDK-EMS Service and the Sentinel LDK-EMS database on two separate machines.

- > ["Sentinel LDK-EMS Web Portals on Separate Servers" on page 44](#)

Installation of the Sentinel LDK-EMS Vendor web portal and the Customer web portal on two separate machines. The Sentinel LDK-EMS database is installed together with the Vendor web portal or on a third machine.

### Standard Production Configuration for Sentinel LDK-EMS

Sentinel LDK-EMS Service and the SQL server for the Sentinel LDK-EMS database are each installed on a separate machine. Sentinel LDK-EMS Service is protected by an external firewall.

#### In this section:

- > ["Installing Sentinel LDK-EMS" below](#)
- > ["Configuring the Firewall" below](#)
- > ["Main Points of the Standard Production Configuration" on the next page](#)
- > ["Configuration Summary" on the next page](#)

---

### Installing Sentinel LDK-EMS

1. On one machine, create an SQL database with a user name and password. The user must have SQL sysadmin or dbcreator privileges for this database.  
For more information, see ["Installing and Configuring SQL Server Manually \(Optional\)" on page 23](#).
2. On a second machine, run the Sentinel LDK-EMS installation procedure. In the procedure, ensure the following:
  - a. Select only **Sentinel LDK-EMS** for installation. It is not necessary to install **Sentinel Vendor Suite**.
  - b. Select the **Advanced** setup type.
  - c. In the Sentinel LDK-EMS Database Configuration screen, specify the information for the SQL database you created earlier.
  - d. Select **Use existing database**.

The full Sentinel LDK-EMS installation procedure is described in ["Installing Sentinel LDK-EMS on Your Machine" on page 22](#).

3. Complete the installation wizard.


Thales recommends that you specify to use the SSL communication protocol.

---

### Configuring the Firewall

An external firewall should be configured to accept requests and to forward only the valid request to Sentinel LDK-EMS.

You can set firewall rules that enables your customers to access Sentinel LDK-EMS, but does not allow them to access the SQL database server, as shown in the diagram that follows.



### Main Points of the Standard Production Configuration

- > End users (customers) and vendor employees have access to a common Application server.
- > Differentiation is by authentication and authorization (access rights).
- > External end users can access only a selected URL.
- > The Sentinel LDK-EMS database can be accessed only by the internal network of the vendor.

### Configuration Summary

- > Deploy Sentinel LDK-EMS Service and MS SQL Server for the Sentinel LDK-EMS database on two separate machines.
- > Use an external firewall. Configure the firewall to allow only for the customer URL (set of URL expose only for Customer access).
- > Place the web server (Sentinel LDK-EMS Service with Tomcat) and the SQL Server inside the firewall.
- > The Sentinel Master key must be attached to the machine where Sentinel LDK-EMS Service is installed.

### Sentinel LDK-EMS Web Portals on Separate Servers

The Sentinel LDK-EMS web front consists of two portals:

- > For vendor users
- > For customers (primarily used for activation)

These Sentinel LDK-EMS portals are usually installed on a single machine (as described in the previous section). However, you can choose to configure Sentinel LDK-EMS so that each portal and the Sentinel LDK-EMS database are all installed on separate machines.

Each server listens on a TCP port for incoming requests. The requests are encrypted using the SSL feature if configured accordingly. Each server then communicates with the Sentinel LDK-EMS database (a single database for the entire system) to process the requests.

#### In this section:

- > ["Installing Sentinel LDK-EMS" below](#)
- > ["Configuring the Firewalls" on the next page](#)
- > ["Main Points of the Separate Portals Configuration" on the next page](#)
- > ["Configuration Summary" on the next page](#)

### Installing Sentinel LDK-EMS

1. On one machine, create an SQL database with a user name and password. The user must have SQL sysadmin or dbcreator privileges for this database.  
For more information, see ["Installing and Configuring SQL Server Manually \(Optional\)" on page 23](#).
2. For the Vendor portal: On a second machine (or the same machine), run the Sentinel LDK-EMS installation procedure. In the procedure, ensure the following:
  - a. Select only **Sentinel LDK-EMS** for installation. It is not necessary to install **Sentinel Vendor Suite**.
  - b. Select the **Advanced** setup type.
  - c. In the Sentinel LDK-EMS Database Configuration screen, specify the information for the SQL database you created earlier.
  - d. Select **Use existing database**.

The Sentinel LDK-EMS installation procedure is described in ["Installing Sentinel LDK-EMS on Your Machine" on page 22](#).
3. Complete the installation wizard.  
Thales recommends that you specify to use the SSL communication protocol.
4. For the Customer portal: On a separate machine, run the Sentinel LDK-EMS installation procedure again. In the procedure, ensure the following:
  - a. Select only **Sentinel LDK-EMS** for installation. It is not necessary to install **Sentinel Vendor Suite**.
  - b. Select the **Advanced** setup type.
  - c. In the Sentinel LDK-EMS Database Configuration screen, specify the information for the SQL database you created earlier.
  - d. Select **Use existing database**.
5. Complete the installation wizard.  
Thales recommends that you specify to use the SSL communication protocol.  
No additional configuration is required.

6. On the Customer portal machine: configure Sentinel LDK-EMS so that the installation can only be accessed using a customer-related URL (requests which are only applicable to the Customer portal). This configuration is a manual process. Contact Thales Professional Services for assistance to perform the required configuration.

## Configuring the Firewalls


The external firewall should be configured to accept only requests that are related to the Customer portal. The requests should be forwarded to the instance of Sentinel LDK-EMS Service that acts as the Customer portal. Sentinel LDK-EMS Service then accesses the remote Sentinel LDK-EMS database through the internal firewall.

The Sentinel LDK-EMS Vendor portal and the Sentinel LDK-EMS database could be installed on a single machine or on two separate machine inside the internal fire wall.

External access to the Vendor portal should be blocked by the external firewall.

All access to the Sentinel LDK-EMS database and the Vendor portal should be only through the internal firewall.

The diagram that follows shows the configuration described in this section.



## Main Points of the Separate Portals Configuration

- > End users (customers) and vendor employees access Sentinel LDK-EMS on different application servers.
- > Differentiation is by authentication and authorization (access rights).
- > External end users can access only the Customer portal of Sentinel LDK-EMS using a selected URL.
- > Internal vendor users can access the Vendor portal of Sentinel LDK-EMS.
- > The Sentinel LDK-EMS database can be accessed only by the internal network of the vendor.

## Configuration Summary

- > Deploy Sentinel LDK-EMS Service as a Vendor portal and as a Customer portal on two separate machine

- > Deploy MS SQL Server for the Sentinel LDK-EMS database inside the internal firewall, on a separate machine or on the same machine as the Vendor portal.
- > Use two proxies (internal and external).
- > Configure the external proxy to allow only for the customer URL (set of URLs exposed only for Customer access), to allow access to the Customer portal.
- > Set up Sentinel LDK-EMS Service for the Customer portal to access only the Sentinel LDK-EMS database and only through the internal firewall.
- > Place the instance of Sentinel LDK-EMS Service for the Vendor portal inside the internal firewall
- > Place the SQL server behind the internal proxy.
- > A Sentinel Master key must be attached to each machine where Sentinel LDK-EMS Service is installed.

## Troubleshooting a Sentinel LDK-EMS Installation

This section describes issues that might occur during or after the installation of Sentinel LDK-EMS (on-premises) and provides possible solutions.

### In this section:

- > ["Problems During Installation" below](#)
- > ["Problems After Installation" on page 49](#)
- > ["Frequently-Asked Questions" on page 50](#)

### Problems During Installation

This section describes problems that may occur during the installation process for Sentinel LDK-EMS.

---

#### Issue: During Sentinel LDK-EMS installation, the following message is displayed:

**Kindly Start the Service -SQLServer(EMSDATABASE) and then click OK**

When you click **OK**, the installation fails with multiple errors.

#### Solution:

Your machine contains earlier versions of JRE, and you manually installed JRE 8 in addition to the earlier versions.

Uninstall the earlier versions of JRE, and then rerun the Sentinel LDK Installation Wizard to install Sentinel LDK-EMS.

### Issue: During Sentinel LDK-EMS installation, the following message is displayed:



#### Solution:

Check which version of Windows Installer (from Microsoft) is present on your machine. (From the Start menu, Click **Run**. In the Open Box, type `msiexec.exe` and click **OK**. The Windows Installer screen is displayed. The version appears on the first line of the screen.)

If the version on your machine is earlier than 4.5, download and install version 4.5 from the Microsoft web site.

### Issue: The Sentinel LDK-EMS installer detects an earlier version and attempts to remove it, but fails.

#### Solution:

Do one of the following:

- > If Sentinel LDK-EMS is visible in the **Programs and Features** screen (which you can access from the Control Panel), remove it from there. Restart the installation.
- > If Sentinel LDK-EMS is not visible in the **Programs and Features** screen or if it is not successfully uninstalled by removing it:
  - a. From the Windows Start menu, select **Run** and enter **regedit**. The Registry Editor is displayed.
  - b. Locate and delete the following entry:
    - 32-bit machine:
    - HKEY\_LOCAL\_MACHINE\SOFTWARE\SafeNet\Sentinel EMS**
    - 64-bit machine:
    - HKEY\_LOCAL\_MACHINE\Software\Wow6432Node\Safenet\Sentinel EMS**
  - c. Locate and delete the following entry:
    - 32-bit machine:
    - HKEY\_LOCAL\_MACHINE\SOFTWARE\SafeNet\Sentinel EMS**
    - 64-bit machine:
    - HKEY\_LOCAL\_MACHINE\Software\Wow6432Node\Safenet\Sentinel EMS**
  - d. Restart the installation.



---

**Issue: Installation of Sentinel LDK-EMS failed.****Solution:**

Do one or more of the following:

- > Check if the operating system on the machine is supported for Sentinel LDK-EMS installation.
- > Check log files at **%Systemdrive%\EMS\_log\** to see if any issues are listed.
- > Make a note of the step at which the installation failed. Report the issue to Technical Support.

---

**Issue: Miscellaneous problems****Previous uncompleted installation of Sentinel LDK-EMS**

The machine on which Sentinel LDK-EMS is being installed may have some previous incomplete installation / removal of software in an incomplete state.

This could be due to any software, including Sentinel LDK-EMS.

**Solution:**

Boot your system before trying to install Sentinel LDK-EMS.

**Problems After Installation**

This section describes problems that may occur after successfully installing Sentinel LDK-EMS.

---

**Issue: The Login button on the Login screen does not function**

Due to high security settings in the web browser, the Login button on the login screen of Sentinel LDK-EMS does not work.

**Solution:**

In your web browser, do the following:

1. From the menu bar, go to **Tools > Internet Options**. A dialog is displayed.
2. Click the **Security** tab.
3. Click **Sites** and add the URL of Sentinel LDK-EMS to the list of trusted sites.
4. Apply the changes and restart your browser.

This problem has been seen under Windows Server 2003 and Windows Server 2008.

---

**Issue: Port not available**

Given the following situation:

- > A user is not able to access the Sentinel LDK-EMS site (localhost/ems)

- > In the Services screen, Sentinel LDK-EMS Service has the status **Started**.

This can be caused by a port conflict. The HTTP/HTTPS port for Sentinel LDK-EMS may be in use by another application.

Check the Sentinel LDK-EMS log file. This can be found at:

%ProgramFiles(x86)%\Thales\Sentinel EMS\EMSServer\webapps\ems\log\

(For 32-bit machines: %ProgramFiles%\....)

If the log file shows a “JVM binding” issue, this indicates that the port used by the Sentinel LDK-EMS web application run is in use by another application.

### Solution:

To resolve a port conflict:

Use the Netstat command to identify which application has occupied the required port. Do one of the following:

- > Stop the conflicting application as follows:
  - Enter: `netstat -aon | findstr "8080"`  
The relevant process ID is displayed.
  - Use the Task Manager to cancel the process with this process ID.
  - Restart Tomcat.
- > Configure Sentinel LDK-EMS to use a different port.  
Modify the port used by Sentinel LDK-EMS in the web\_service.xml file and the database.
- > Remove and then reinstall Sentinel LDK-EMS (removal does not remove the Sentinel LDK-EMS database).

### Issue: Users are not able to access Sentinel LDK-EMS

### Solution:

Sentinel LDK-EMS Service may be installed behind a firewall, and it was not added in the exception list for the firewall.

### Frequently-Asked Questions

This section describes and answers some of the frequently asked questions relating to the installation of Sentinel EMS (on-premises) in a network environment.

#### Can I use a non-system administrator (sa) account?

Yes, you can use a non-system administrator account as follows:

1. Open the Microsoft SQL Server Management utility and create a new login. Ensure that:
  - The login uses SQL server authentication
  - The defined database is the Sentinel LDK-EMS database (by default, EMSDB)

- User mapping maps the login to the Sentinel LDK-EMS database, enabling all roles except db\_denydatawriter and db\_denydatareader
2. Edit all the configuration files and change the `CONNECT_STRING` parameters as follows:
    - Change **uid** to the login name that you defined
    - Change **pwd** to the password that you defined

Note that this string is displayed many times in the configuration files and must be changed in every instance.

The configuration files are:

- context.xml
  - ems-quartz.xml
  - ems.properties
  - emsconfig.properties
3. Restart the server.
  4. Check the connection by entering the following URL in your browser:  
`https://<server>:<port>/ems/` (OR `http://<server>:<port>/ems/`)

The test will return a **Database connection: PASSED** message.

#### How can I best secure my Sentinel LDK-EMS system?

- > Implement the standard IT information security protocols that are applicable to your organization.
- > Ensure that only the TCP port number, as defined for HTTP/HTTPS ports configured in Tomcat, are accessible.
- > Ensure that only Sentinel LDK-EMS can access the SQL database.
- > Change the default admin password. For details, see the [Sentinel LDK-EMS User Guide](#).
- > Ensure that personnel in your organization are designated appropriate roles in Sentinel LDK-EMS, and that their accounts are inaccessible when they are no longer part of the organization. For more information about assigning roles, see the [Sentinel LDK-EMS User Guide](#).

# CHAPTER 3: Introducing Your Sentinel Vendor Keys to Sentinel LDK

When you order Sentinel protection keys from Thales, you are assigned a unique Batch Code. Your Batch Code represents your unique confidential Vendor Code.

Your Sentinel LDK Starter Kit contains a Sentinel LDK Master key and a Sentinel LDK Developer key (referred to collectively as *Sentinel Vendor keys*). Each Sentinel Vendor key contains your unique Vendor Code.

You must "introduce" one of your Vendor keys to Sentinel LDK using the Sentinel LDK Master Wizard to be able to perform a number of important functions as described in ["Master Wizard Functions" below](#).

If you have multiple Batch Codes, you must introduce one of your Vendor keys for each Batch Code.

You must introduce one of your Sentinel Vendor keys to the system:

- > Before you use Sentinel Vendor Suite for the first time.
- > After each time you upgrade to a new version of Sentinel LDK.

This ensures that your applications are protected and licensed with the unique codes that have been assigned to you and that you are working with the latest APIs and libraries. The Sentinel Vendor keys are introduced using Sentinel LDK Master Wizard.

**NOTE** The Sentinel LDK Master key is required only when working with Sentinel LDK-EMS (on-premises). Vendors who are working with Sentinel EMS or Sentinel LDK-EMS (hosted by Thales) can handle all functions using the Sentinel LDK Developer key.

For more information about Batch Codes, see the description of personalized Vendor and Batch Codes in the [Sentinel LDK Software Protection and Licensing Guide](#).

## Master Wizard Functions

This section describes the functions performed by the Master Wizard and the machines on which the Master Wizard must be run for each function.

The Master Wizard performs one or more of the following:

### > Configure Sentinel LDK-EMS

**NOTE** This function is relevant for Sentinel LDK-EMS (hosted by Thales or on-premises). This is not relevant for Sentinel EMS.

The wizard performs the following:

- Registers a new Batch Code in Sentinel LDK-EMS. This is required so that Sentinel LDK-EMS will recognize the Batch Code and perform actions for that Batch Code.
- Downloads vendor-specific APIs and the vendor library from Thales servers to Sentinel LDK-EMS so that customized RTE installers will be available for download from the **Developer** tab in Sentinel LDK-EMS.

You can run the Master Wizard on any machine that can connect to Sentinel LDK-EMS (hosted by Thales or on-premises).

Run the Master Wizard before you start working with Sentinel LDK-EMS. Thales recommends that you rerun the Master Wizard after each new release of Sentinel LDK.

#### > **Download vendor-specific APIs and the vendor library**

The wizard downloads vendor-specific APIs and the vendor library from Thales servers. These are generated individually for each Batch Code and are used by Sentinel LDK Envelope and Licensing API to implement license enforcement.

Run the Master Wizard on each machine where you have installed Vendor Suite.

Run the wizard before you start working with Sentinel LDK-EMS. Thales recommends that you run the Master Wizard after each new release of Sentinel LDK.

#### > **Generate customized RTE installers**

The wizard downloads Run-time Environment (RTE) installers from Thales servers and customizes them on your machine. The Master Wizard customizes the installers by embedding your vendor library and the server address for Sentinel EMS or Sentinel LDK-EMS.

The installers are saved to:

*%UserProfile%\Documents\Thales\Sentinel LDK <version>\Redistribute\Runtime Environment*

These installers can be distributed to:

- Customers who require the Run-time Environment to access protection keys.
- (Under Windows) Customers who will use the Sentinel LDK-EMS Customer Portal to activate or update licenses.

Run the Master Wizard on any machine where the Sentinel LDK launcher is installed.

Thales recommends that you run the Master Wizard after each new release of Sentinel LDK or of the Run-time Environment.

## Methods of Introducing a Vendor Key

---

You can introduce your Vendor key using either of the following methods:

#### > **Download over the Internet**

Using this method, the Master Wizard connects to the Thales server over the Internet and downloads the required files to your machine. This is the easiest method.

➤ **Extraction from a Master Wizard Package**

If the machine where you want to introduce a Vendor key cannot connect to the Internet, you can request a Master Wizard Package (MWP) file from Thales customer services. You will receive an MWP file that was generated specifically for your Batch Code and contains all of your customized libraries and RTE installers. The Master Wizard reads this file and extracts the libraries and installers that you select.

You select your preferred method of introduction when you run the Master Wizard.

## Remote Connection of Vendor Keys

---

Sentinel Master key (for Sentinel LDK-EMS on premises) and Developer keys can be connected remotely using available third-party solutions. These solutions can be used in cases where a physical key cannot be connected due to the lack of a USB port or inability to physically access the machine. You can connect your Master or Developer keys to an over-the-network USB solution and access them from any physical or virtual machine as if they were connected locally.

There are several such solutions, both software-based (that can be installed on any PC with a USB port) and dedicated devices. Among the dedicated devices, Thales recommends utnserver Pro, myUTN-2500, dongleserver Pro, and dongleserver ProMAX by SEH Technology. These devices were tested for Thales Sentinel HL keys, and are backed by partnership between SEH Technology and Thales.

## Selecting the Version-Enforcement Option

---

API libraries that are customized for your vendor code are used by Sentinel LDK Envelope and Sentinel Licensing API to protect your applications. These libraries are generated by Thales specifically for your Batch Code. You download these customized vendor libraries using the Master Wizard when you introduce your Vendor keys.

The Master Wizard offers you a choice of two types of libraries, each incorporating one of the options described below. The option that you select determines how protected applications interact with the Run-time Environment (the RTE). The available options are:

➤ **Version-restricted option** (Recommended for best security and reliability in the protected application)

For protected applications that require the RTE: With the version-restricted option, the applications will require a *minimum version* of the RTE (the earliest version that contains the latest important security and reliability enhancements). Use of the version-restricted option ensures that end users cannot downgrade to an earlier version of the RTE and that they use a version of the RTE that provides the best quality together with all the latest security and reliability fixes. This restriction applies both for local deployment of the RTE and for deployment of the RTE on a remote license server machine.

For each new release of Sentinel LDK, the required *minimum version* number is updated only if the RTE for that release contains significant security and reliability enhancements.

**Example:** The required *minimum version* of the RTE for applications protected with versions 7.9 through 8.0 of the customized vendor libraries remains as RTE version **7.90**, because this version of the RTE contains the latest significant security and reliability enhancements. Later versions of the RTE contain less important enhancements and fixes.

**NOTE** The version-restricted option is only relevant for the static Licensing API because the user can replace the new version of the dynamic Licensing API with an older version.


**Example:** Given that the dynamic Licensing API version 8.1 has a security issue. The vendor downloads the version-restricted dynamic Licensing API 8.2 using the Master Wizard, and then releases the new version of the dynamic Licensing API. However, a user can bypass any new security enhancements in the new version if they can obtain the old version of the dynamic Licensing API and replace the new version.

> **Version-unrestricted option** (For compatibility with all versions of the RTE)

For protected applications that require the Run-time Environment: The applications will not check the version number of the RTE. Applications protected with this option can be used with all versions of the RTE. Select this option only if you want to avoid upgrading the RTE at end user sites. This option simplifies deployment, especially when network license servers are used, but does not guarantee that security and reliability fixes in later RTE versions are employed.

**NOTE** With either option, users will need to upgrade their RTE if the protected application uses specific functionalities that require a later version of the RTE.

The diagram that follows illustrates how this process operates.



For more information, see “Required Version of the Run-time Environment” in the [Sentinel LDK Software Protection and Licensing Guide](#).

## Using the Master Wizard to Introduce a Sentinel Vendor Key

Perform the procedure that follows to run the Sentinel LDK Master Wizard and introduce one of the Sentinel Vendor keys (Master Key or Developer Key).

**NOTE** You can use either a Developer key or a Master key with the relevant Batch Code to perform this process. There is no requirement to use a specific key. However:

- > To generate licenses using Sentinel LDK-EMS (on-premises), the Master key must be left connected to the local machine where Sentinel LDK-EMS is installed.
- > To protect applications, a Developer key must usually be left connected to each machine where Sentinel LDK Envelope is used.



**To introduce a Sentinel Vendor key:**

1. **Prerequisite:** Choose the machine on which to run the Master Wizard and decide what you want to accomplish before starting this procedure. For details, see ["Master Wizard Functions" on page 52](#).
2. For Sentinel LDK-EMS (on-premises): In the Windows Services window, ensure that the Sentinel LDK-EMS Service is active.
3. Connect a Vendor key to the relevant machine in one of the following ways:
  - Connect the key to the machine locally.
  - Connect the key to the machine using a remote USB solution as described in ["Remote Connection of Vendor Keys" on page 54](#).
4. From the Start menu, select: **Thales > Sentinel LDK**. The Sentinel LDK Launcher program selection screen is displayed.
5. From the Sentinel LDK Launcher screen, choose **Additional Tools > Sentinel Master Wizard**.

**NOTE** If you open either Sentinel LDK Envelope or Sentinel LDK ToolBox, and the application detects a Vendor key with a new Batch Code, the Master Wizard starts automatically.

The Log In to Sentinel EMS or LDK-EMS window is displayed:

6. Enter the user name and password as follows:

- For Sentinel LDK-EMS: If you are running the wizard to configure Sentinel LDK-EMS (as described in ["Master Wizard Functions" on page 52](#)), enter the user name and password for an EMS administrator; otherwise, leave these fields blank.
  - For Sentinel EMS: Leave these fields blank.
7. If you are configuring Sentinel LDK-EMS (hosted by Thales or on a remote machine) or you want to generate customized RTE installers (as described in ["Master Wizard Functions" on page 52](#)):
- Click **Advanced**. Use these additional fields to specify public information for accessing Sentinel EMS or LDK-EMS from your customers' machines.


- In **Server Address**: Specify the URL for accessing Sentinel EMS or Sentinel LDK-EMS
- In **Port**:
  - For Sentinel EMS or Sentinel LDK-EMS (Thales-hosted), enter **443**.
  - For Sentinel LDK-EMS (on-premises), enter **8080** or the port as configured for your site.
- In **Use SSL**:
  - For Sentinel EMS or Sentinel LDK-EMS (Thales-hosted), select the check box.
  - For Sentinel LDK-EMS (on-premises), select or clear the check box as configured for your site.

**NOTE** For Sentinel LDK-EMS (on-premises): If the public information provided in the fields above cannot be used to access your on-premises Sentinel LDK-EMS server within your network, you must run the Master Wizard a second time to configure Sentinel LDK-EMS:

- First, complete the wizard and save the customized RTE installers generated by the wizard to a different location.
- Next, run the wizard again to configure Sentinel LDK-EMS. In the Advanced fields above, specify the information for accessing the Sentinel LDK-EMS server in your local network.

8. If you provided a user name and password above, click **Login**. Otherwise, click **Skip login**.


The following screen is displayed:



9. Select the desired method for introducing your Vendor key. For more information, see ["Methods of Introducing a Vendor Key" on page 53](#).


10. Click **Next**. (If you chose the "Extract" method above, the wizard asks you to browse to and select your MWP file.)

The following screen is displayed:



11. Select the **version-restricted** or **version-unrestricted** option (see "[Selecting the Version-Enforcement Option](#)" on page 54). Click **Next**.

The following screen is displayed:



**Sentinel LDK Master Wizard** **THALES**

**Specify Sentinel Vendor Key**

Ensure that you keep this key secure and in a safe place. It contains your confidential Vendor Codes.

Key ID: 591751674 (Master key) ▼

Batch Code: KQIBZ


Vendor ID: 37517

Vendor Code: C:\Users\haoyang\Documents\Gemalto\Sentinel LDK 8.0\VendorCodes\KQIBZ.hvc ...

< Back Next > Cancel

12. Ensure that the Key ID for the relevant Vendor key is displayed. Click **Next**.

The following screen is displayed:



**Sentinel LDK Master Wizard** **THALES**

**Specify API Settings**

Select the libraries for which you want to download APIs. By default, the wizard downloads a separate API for each Batch Code.

Close any running Vendor Suite application before downloading APIs.

Library Type

- ☒ Windows
  - ☒ API - 32 Bit Windows Static (8.23.8.119204)
  - ☒ API - 32 Bit Windows DLL (8.23.8.119204)
  - ☒ API - 32 Bit Windows Static for Borland (8.23.8.119204)
  - ☒ API - 64 Bit Windows Static (8.23.8.119204)
  - ☒ API - 64 Bit Windows DLL (8.23.8.119204)
  - ☒ API - 32 Bit Windows Delphi static object (8.23.8.119204)
  - ☒ Sentinel LDK VendorSuite Tool API (8.23.8.119204)
  - ☒ API - 64 Bit Delphix API (8.23.8.119204)
  - ☒ API - 32 Bit Delphix API (8.23.8.119204)
  - ☒ VLIB - Windows Vendor Library (8.23.1.119204)
  - ☒ RTE - Windows RTE Command Line (8.31.100)

< Back Next > Cancel

- 13.** Select the libraries for which you want to generate APIs and select the Run-time Environment installers that you want to download and configure (some items are selected by default and cannot be cleared).

**NOTE** The Specify API Settings screen is always displayed and the selected items downloaded each time you run the Master Wizard. Ignore these items if you do not need them on the machine where you are running the wizard.

- 14.** Click **Next**.

- The generated APIs are downloaded to the following directory, under the appropriate subdirectory:  
%UserProfile%\Documents\Thales\Sentinel LDK 8.3\API\Runtime\
- The configured Run-time Environment installers are downloaded to:  
%UserProfile%\Documents\Thales\Sentinel LDK 8.3\Redistribute\Runtime\

- 15.** Click **Finish** to close the wizard.

# CHAPTER 4: Installing Sentinel LDK Run-time Environment

This section describes how to install Sentinel LDK Run-time Environment on the following platforms.

- > ["Installing Sentinel LDK Run-time Environment for Mac" below](#)
- > ["Installing Sentinel LDK Run-time Environment for Linux" on page 66](#)
- > ["Installing Sentinel LDK Run-time Environment for Windows" on page 71](#)

## Installing Sentinel LDK Run-time Environment for Mac

This section describes how to install the Sentinel LDK Run-time Environment on a machine with a Mac operating system, and explains how to modify the behavior of the daemons.

For information on supported platforms for Sentinel LDK Run-time Environment, see the [Sentinel LDK Release Notes](#).

### In this section:

- > ["Installing Sentinel LDK Run-time Environment" below](#)
- > ["Installed Files" on the next page](#)
- > ["Modifying the Behavior of the Daemons" on the next page](#)

## Installing Sentinel LDK Run-time Environment

Follow the instructions below to install the Sentinel LDK Run-time Environment on a machine with a Mac operating system.

### To install the Sentinel LDK Run-time Environment:

1. Go to the Sentinel LDK *MacOS* directory on your Mac machine. For more information see the [Sentinel LDK Getting Started Guide for Mac](#).
2. Open `/MacOS/Redistribute`, and double-click `Sentinel_Runtime.dmg`.
3. Double-click the *Install Sentinel Runtime Environment* disk image icon. The installer wizard is launched.
4. Follow the instructions of the installer wizard until the installation is complete.

Following successful installation, the Sentinel LDK Run-time Environment is automatically launched. The first time that you run Admin Control Center and submit configuration changes, **hasplmd** creates configuration files in */private/etc/hasplm/*.

## Installed Files

After you run the installation, verify that the following files have been installed on your hard drive:

- > */usr/local/sentinel/aksusbd* (support for Sentinel HL (HASP configuration) keys and HASP HL keys)
- > */usr/local/sentinel/hasplmd* (Sentinel License Manager daemon)
- > */Library/LaunchDaemons/com.aladdin.aksusbd.plist*
- > */Library/LaunchDaemons/com.aladdin.hasplmd.plist*

## Modifying the Behavior of the Daemons

Behavior of the daemons can be modified by changing the switches used to start the daemons. Modification requires the following steps:

- > Terminating the daemons
- > Determining the switches to use
- > Saving the modifications
- > Restarting the daemons

### To terminate the daemons:

1. Ensure that you have Administrator privileges.
2. Launch */Applications/Utilities/Terminal*.
3. Change the directory to: */Library/LaunchDaemons/*
4. At the command prompt, enter the following commands:

```
sudo launchctl unload com.aladdin.hasplmd.plist
```

```
sudo launchctl unload com.aladdin.aksusbd.plist
```

(When prompted, enter your administrator password.)

The daemons stop running.

### To determine which switches to use:

Use the table that follows to determine which command line switches to use to set the behavior of the **aksusbd** and **hasplmd** daemons.



Daemon	Command	Description
Both	-f	Forces the daemon to work in the foreground. Required for launchd startup.
Both	-h, --help	Displays a list of available commands
Both	-l <level>	Specifies the level of log messages. The values are: 0 - Errors only 1 - Normal 2 - Verbose 3 - Ultra verbose
Both	v	Displays aksusbd and API versions OR Displays hasplmd version
aksusbd	-d <milliseconds>	Specifies the delay after connecting a Sentinel HL (HASP configuration) key or HASP HL key, before it can be accessed the first time (range 0–2000)
aksusbd	-q <entries>	Specifies the length of the work queue (default 64)
aksusbd	-u <mask>	Specifies the permission bits for the special socket file. Default is 666 (access for all users)
aksusbd	-s <file>	Specifies the communication socket name
hasplmd	-s, -start	Starts the Sentinel License Manager daemon
hasplmd	-u <user>	Launches daemon with owner as user to enhance security

### To save the selected switches:

After determining which switches you want to employ, do the following to save the switches in the **.plist** files so that they will be used each time the daemons are launched when the system is restarted:

- > Either edit the relevant **.plist** files using a text editor OR use the /Developer/Applications/Utilities/Property List Editor (part of the Xcode Developer Tools) to do the following:
  - a. Add the modifications for **aksusbd** to */Library/LaunchDaemons/com.aladdin.aksusbd.plist*.
  - b. Add the modifications for **hasplmd** to */Library/LaunchDaemons/com.aladdin.hasplmd.plist*.

Ensure that the **-f** switch is included in both daemons.

**To restart the daemons:**

After saving the selected switches, do the following to restart the daemons:

1. Ensure that you have Administrator privileges.
2. Launch */Applications/Utilities/Terminal*.
3. Change the directory to: */Library/LaunchDaemons/*
4. At the command prompt, enter the following commands

```
sudo launchctl load com.aladdin.aksusbd.plist
```

```
sudo launchctl load com.aladdin.hasplmd.plist
```

(Enter your Administrator password when prompted.)

The daemons are restarted.

**NOTE** The Run-time Environment daemons are launched automatically when the system is restarted.

## Installing Sentinel LDK Run-time Environment for Linux

This section describes how to install Sentinel LDK Run-time Environment v.8.31.1 on a computer with a Linux operating system.

For information on supported platforms for Sentinel LDK Run-time Environment, see the [Sentinel LDK Release Notes](#).

**In this section:**

- > ["Installing Sentinel LDK Run-time Environment" on the next page](#)
- > ["Installed Files" on page 70](#)
- > ["Uninstalling Sentinel LDK Run-time Environment" on page 70](#)
- > ["Upgrading HASP HL Key Firmware" on page 71](#)

## Installing Sentinel LDK Run-time Environment

**NOTE** When installing Sentinel LDK Run-time Environment on an end user's machine: To support your application on both 32-bit and 64-bit architectures, ensure that you provide both 32-bit and 64-bit customized Vendor libraries with the Run-time Environment installer. These libraries are contained in the following files:

- > haspvlib\_<vendorID>.so
- > haspvlib\_x86\_64\_<vendorID>.so
- > haspvlib\_armhf\_<vendorID>.so
- > haspvlib\_arm64\_<vendorID>.so

### To install the Sentinel LDK Run-time Environment using RPM or DEB:

1. Go the Sentinel LDK *Linux* directory on your Linux machine. For more information see the [Sentinel LDK Getting Started Guide for Linux](#).
2. Disconnect your Sentinel HL key (if any) from the machine.
3. Open a terminal window and navigate to *Linux/Redistribute/Runtime*.
4. As root, enter the following command:

- For RedHat, SUSE, or CentOS 32-bit ARM systems:

```
rpm -i aksusbd-8.31-1.armv7hl.rpm
```

- For RedHat, SUSE, or CentOS 64-bit ARM systems:

```
rpm -i aksusbd-8.31-1.aarch64.rpm
```

- For RedHat, SUSE, or CentOS 64-bit Intel systems:

```
rpm -i aksusbd-8.31-1.x86_64.rpm
```

- For Ubuntu or Debian 32-bit ARM systems:

```
dpkg -i aksusbd_8.31-1_armhf.deb
```

- For Ubuntu or Debian 64-bit ARM systems:

```
dpkg -i aksusbd_8.31-1_arm64.deb
```

- For Ubuntu or Debian 64-bit Intel systems:

```
dpkg -i aksusbd_8.31-1_amd64.deb
```

**NOTE** All install/uninstall commands must be executed with **root** rights. In Ubuntu, prefix the commands with the **sudo** command; in other distributions, use the **su** utility to become root in the terminal window.

The Sentinel LDK Run-time Environment is launched.

5. Reconnect the Sentinel HL key.

**NOTE** At this point, for older HASP HL keys, the firmware on the HL key may be automatically upgraded. During the upgrade process, the key will blink continuously. *Do not remove the key while it is blinking.* If you remove the key too soon, the key may no longer be visible in Admin Control Center. If the key is not visible, or if the upgrade does not occur, see ["Upgrading HASP HL Key Firmware" on page 71](#).

**To install the Sentinel LDK Run-time Environment from a script:**

(Use this procedure if the distribution does not support RPM or DEB.)

1. Go the Sentinel LDK *Linux* directory on your Linux machine. For more information see the [Sentinel LDK Getting Started Guide for Linux](#)
2. Disconnect your Sentinel HL key (if any) from the machine.
3. Copy the package **Linux/Redistribute/Runtime/aksusbd-8.31.1.tar.gz** to a local directory.
4. Open a terminal window in the local directory.
5. Enter the following command to uncompress the package containing the Run-time Environment installer:

```
tar zxvf aksusbd-8.31.1.tar.gz
```

6. Enter the following command to change to the directory containing the installer:

```
cd aksusbd-8.31.1
```

7. As **root**, enter the command: `./dinst`

The Sentinel LDK Run-time Environment is launched.

8. Reconnect the Sentinel HL key.

**NOTE** At this point, for older HASP HL keys, the firmware on the HL key may be automatically upgraded. During the upgrade process, the key will blink continuously. *Do not remove the key while it is blinking.* If you remove the key too soon, the key may no longer be visible in Admin Control Center. If the key is not visible, or if the upgrade does not occur, see ["Upgrading HASP HL Key Firmware" on page 71](#).

### Uninstalling Run-time Environment v.1.14 or Earlier

An existing installation of the Run-time Environment v.1.14 or earlier cannot be upgraded and must therefore be uninstalled. (Run-time Environment v.1.15 or later *can* be upgraded.)

Before installing the new Run-time Environment, enter the following command to uninstall an existing Run-time Environment v.1.14 or earlier (if present):

> For RedHat: `rpm -e aksusbd-redhat`

> For SUSE: `rpm -e aksusbd-suse`

If the existing Run-time Environment was installed using the Run-time Environment installation script (**dinst**), remove this installation by entering following command as **root** from within the script package: **./dunst**

## Installed Files

After you run the installation, verify that the following files are installed:

- > `/usr/sbin/aksusbd` and `/usr/sbin/aksusbd_x86_64`

32-bit and 64-bit support for Sentinel HL (HASP configuration) keys and HASP HL keys, and support for low-level access to the Sentinel License Manager daemon.

- > `/etc/init.d/aksusbd` or `/etc/init.d/aksusbd_x86_64`

32-bit or 64-bit startup script for Sentinel License Manager daemon. This file is not installed for Linux systems that use **systemd**. The file is installed only for old systems that use **sysv**.

- > `/usr/sbin/hasplmd` and `/usr/sbin/hasplmd_x86_64`

32-bit and 64-bit Sentinel License Manager daemons

- > `/etc/udev/rules.d/80-hasp.rules`

Rules for `/udev`

Following successful installation, the Sentinel LDK Run-time Environment is automatically launched. The first time that you run Admin Control Center and submit configuration changes, **hasplmd** creates a **hasplm.ini** configuration file in **/etc/hasplm**. In addition, log files are created in **/var/hasplm/**.

## Uninstalling Sentinel LDK Run-time Environment

**To uninstall Sentinel LDK Run-time Environment v.1.15 or later, when installed using RPM or DEB:**

- > For RedHat, SUSE, or CentOS: As root, enter the command:

```
rpm -e aksusbd
```

- > For Debian or Ubuntu: Enter the command:

```
dpkg -r aksusbd
```

For some earlier Ubuntu systems, it may be necessary to specify that this is an i386 package. Enter the command:

```
dpkg -r aksusbd:i386
```

**To uninstall Sentinel LDK Run-time Environment when installed using “dinst”:**

- > As root, open a terminal window and enter the command:

```
./dunst
```

The **dunst** script can be found in the directory containing the **dinst** script, described in ["Installing Sentinel LDK Run-time Environment" on page 67](#).

## Upgrading HASP HL Key Firmware

The Firmware for older HASP HL keys has been modified to support future planned security enhancements in Sentinel LDK. Sentinel LDK automatically upgrades the Firmware on HASP HL keys from v.3.21 to the latest version (v.3.25). This occurs:

- > when a HASP HL key with v.3.21 Firmware is connected to a computer where the Run-time Environment is being updated to v.1.15.
- > when a customer connects a HASP HL key with v.3.21 Firmware to a computer where the Run-time Environment v.1.15 has been previously installed.

(You can determine the Firmware version of your HL key by viewing the key on the Sentinel Keys page of the Admin Control Center.)

For HL keys with Firmware earlier than version 3.21, the upgrade does not occur automatically. Customers can upgrade the Firmware to version 3.25 by applying the Firmware Update V2C. This is located on the machine where Sentinel LDK Vendor Suite is installed, in the directory:

`%ProgramFiles(x86)\Thales\Sentinel LDK\Redistribute\Firmware Update\HASP HL\`

During the Firmware upgrade, the relevant key will start to blink. Do not remove the key while it is blinking. If you remove the key too soon, the key may no longer be visible in Admin Control Center.

**NOTE** In the event the key is no longer visible using the Linux Run-time Environment, do the following on a Windows computer:

1. Install Sentinel LDK Run-time Environment.
2. Connect the HL key.
3. Run the application **FirmwareUpdate.exe**. This is located in the directory described above. The HL key is upgraded to v.3.25 Firmware and will now be visible in the Linux Admin Control Center.

## Installing Sentinel LDK Run-time Environment for Windows

Sentinel LDK Run-time Environment may be required:

- > at the vendor's site, to perform many activities using Sentinel EMS or LDK-EMS. In this case, the Run-time Environment is typically installed by the Sentinel LDK installer.
- > at the customer's site, to perform online activation of SL AdminMode keys using the Sentinel LDK-EMS Customer Portal.
- > at the customer's site, for your protected applications to run. Depending on the type of protection key provided, the Run-time Environment may be required at the site.

For more information, see the [Sentinel LDK Software Protection and Licensing Guide](#).

This section describes how you can install the Run-time Environment when it is required for your protected application (and it has not been installed automatically from the Customer Portal).

For information on supported platforms for Sentinel LDK Run-time Environment, see the [Sentinel LDK Release Notes](#).

The following utilities are available for installing the Sentinel LDK Run-time Environment at the end user's site:

- > A stand-alone GUI installer (HASPUserSetup.exe)
- > A command line installer that you can integrate into your software installer (haspdinst.exe)

These utilities recognize the operating system in use and install the correct Run-time environment.

**NOTE** Administrator privileges are required to install the Sentinel LDK Run-time Environment.

#### In this section:

- > ["HASPUserSetup.exe Utility" below](#)
- > ["haspdinst.exe Utility" on the next page](#)
- > ["Multiple Installations on a Single End User's Computer" on page 74](#)

## HASPUserSetup.exe Utility

HASPUserSetup.exe is a GUI-based installation program to independently install the Sentinel LDK Run-time Environment. Following installation, the file is located in:

`%ProgramFiles(x86)%\Thales\Sentinel LDK\Redistribute\Runtime Environment\Setup`

To launch the utility, double-click HASPUserSetup.exe and follow the wizard instructions.

**NOTE** The HASPUserSetup.exe utility automatically installs the Run-time Environment with or without legacy drivers, as required. If you need to force installation of legacy drivers, use the ["haspdinst.exe Utility" on the next page](#). For more information, see the description of legacy drivers in the [Sentinel LDK Software Protection and Licensing Guide](#).



## haspdinst.exe Utility

haspdinst.exe is a command-line utility that installs the Sentinel LDK Run-time Environment. Following installation, the file is located in:

%ProgramFiles(x86)%\Thales\Sentinel LDK\Redistribute\Runtime Environment\cmd Install

**NOTE** By default, the haspdinst.exe utility automatically installs the Run-time Environment with or without legacy drivers, as required. If necessary, you can force installation of legacy drivers using the relevant switch described in ["Additional haspdinst.exe Utility Switches"](#) below. For more information, see the description of legacy drivers in the [Sentinel LDK Software Protection and Licensing Guide](#).

### To install or upgrade the Sentinel LDK Run-time Environment:

- > Type `haspdinst -i` in the command line. The installation or upgrade process is performed automatically. A message is displayed informing you that the Sentinel LDK Run-time Environment was successfully installed.

Immediately after the Run-time Environment is installed or upgraded, any V2C file contained in the same folder is applied to the relevant protection key on the machine.

Sentinel LDK Run-time Environment 7.100 or later must be present on the machine for the V2C files to be automatically applied.

### To remove the Sentinel LDK Run-time Environment:

- > Type `haspdinst -r` in the command line. A message is displayed informing you that the Sentinel LDK Run-time Environment was successfully removed.

### Additional haspdinst.exe Utility Switches

The following table lists additional switches that can be used with the haspdinst.exe utility.

Switch	Description
-info	Displays the installation status
-h or -?	Displays a list of the available commands
-kp	Enables the installation program to 'kill' all processes accessing the Run-time Environment
-cm	Sets the installation program to display only critical messages (for example, instructions to reboot)

Switch	Description
-fr	Sets the installation program to remove Sentinel LDK Run-time Environment by force, leaving the run-time in a non-functioning state
-ld	Forces installation of the Run-time Environment with legacy drivers. For details, see the <a href="#">Sentinel LDK Software Protection and Licensing Guide</a> . For example: <code>haspdinst -i -ld</code>
-fi	Sets the installation program to ignore other running Windows processes
-nomsg	Sets program to display no messages
-chkllm	If used in conjunction with the <code>-i</code> or <code>-r</code> switch, checks for active License Manager sessions and prompts the user to continue or to abort the operation.
-fss	Silently stops “HASP Loader” and “Server” services (if they are active), performs the requested operation, and then restarts the services.

## Multiple Installations on a Single End User's Computer

The Sentinel LDK Run-time Environment installer utilities contain an automatic mechanism that prevents more than one copy of the Run-time Environment from being installed on a single computer, even if multiple protected applications are installed on the computer.

The Run-time Environment installer utilities employ a counter that keeps track of the number of protected applications installed on a given computer.

For each installation after the first, the installer simply increments the counter instead of actually installing an additional copy of the Run-time Environment. Similarly, the counter is decremented each time the Run-time Environment is uninstalled.

The Run-time Environment is not actually uninstalled until the last protected application is uninstalled.


## CHAPTER 5: Installing Software Updates

On the Windows machine where Sentinel Vendor Suite or Sentinel LDK-EMS is installed, the Sentinel LDK software manager checks to determine whether a later version of the software is available from Thales servers. This helps to ensure that you are aware of important updates and that you are always working with the latest version of Sentinel LDK.

An update may consist of a new version of Sentinel LDK or an update to individual components or documents.


Each day, the software manager checks for the availability of any updates to the installed components of Sentinel LDK. The check takes place at the same time of day that the components were installed. Only one update notification is delivered on any given day.

If the software manager determines that an update is available, a message window similar to the following is displayed:



The title of the window identifies the component of Sentinel LDK to which the update applies, followed by "Update Client".

For more information regarding the update, click **Show Details**. A window similar to the following is displayed:



This window lists details of the update.

At this point, you can choose to:

- > Click **Install** to download and install the updated version.

**NOTE** Before you click this option, be sure to close any active Sentinel LDK applications.

- > Click **Not Now** (or just close the window) to postpone the update. The notification will be displayed again the next day.
- > Click **Ignore Update**. You will not receive any more notifications regarding this specific update.

# CHAPTER A: Modifying and Uninstalling Sentinel LDK

This appendix describes how to add Sentinel LDK-EMS or Sentinel LDK Vendor Suite to an existing installation of Sentinel LDK, and how to uninstall Sentinel LDK components from your computer.

## Modifying the Installed Sentinel LDK Components

After installing one of the two major Sentinel LDK components, you may want to add the second component on the same machine. For example, you may have installed only Sentinel LDK Vendor Suite, and now you want to add Sentinel LDK-EMS on the same machine (or vice versa).

**To add the second component on the same machine as the first component:**

Run the installation procedure from the Sentinel LDK Installation Drive and select the **Modify** option.

**NOTE** *Do not* use the **Change > Modify** option that is available from the Programs and Features window in the Control Panel.

## Uninstalling Sentinel LDK Vendor Suite

This section describes how to completely uninstall the current version of Sentinel LDK Vendor Suite from your computer. To uninstall earlier versions of Sentinel LDK or Sentinel HASP, see the appropriate version of the Installation Guide.

**To completely uninstall Sentinel LDK Vendor Suite from your computer:**

1. Ensure that all Sentinel LDK components are not active.
2. On the computer where you want to uninstall Sentinel LDK, open the **Programs and Features** window from the Control Panel.
3. Remove the following:
  - Sentinel LDK
  - Sentinel Runtime
  - Sentinel Vendor Suite

## Uninstalling Sentinel LDK-EMS (On-Premises)

---

If you installed Sentinel LDK-EMS on premises, remove Sentinel LDK-EMS as described below.

**NOTE** This procedure does not remove the Sentinel LDK-EMS database.

**To completely uninstall Sentinel LDK-EMS from your computer:**

1. Ensure that Tomcat is not active.
2. Open the **Programs and Features** window from the Control Panel.
3. Remove Sentinel LDK-EMS

# SENTINEL LDK PRODUCT END USER LICENSE AGREEMENT

IMPORTANT INFORMATION - PLEASE READ THIS AGREEMENT CAREFULLY BEFORE USING THE CONTENTS OF THE PACKAGE AND/OR BEFORE DOWNLOADING OR INSTALLING THE SOFTWARE PRODUCT. ALL ORDERS FOR AND USE OF THE SENTINEL® LDK PRODUCTS (including without limitation, the Developer's Kit, libraries, utilities, diskettes, CD\_ROM, DVD, Sentinel keys, the software component of Sentinel LDK, and the Sentinel LDK Software Protection and Licensing Guide) (hereinafter "Product") SUPPLIED BY THALES DIS CPL USA, Inc., or one of its affiliates, (in each case, referred to hereinafter as "THALES") ARE AND SHALL BE, SUBJECT TO THE TERMS AND CONDITIONS SET FORTH IN THIS AGREEMENT.

BY OPENING THE PACKAGE CONTAINING THE PRODUCTS AND/OR BY DOWNLOADING THE SOFTWARE (as defined hereunder) AND/OR BY INSTALLING THE SOFTWARE ON YOUR COMPUTER AND/OR BY USING THE PRODUCT, YOU ARE ACCEPTING THIS AGREEMENT AND AGREEING TO BE BOUND BY ITS TERMS AND CONDITIONS.

IF YOU DO NOT AGREE TO THIS AGREEMENT OR ARE NOT WILLING TO BE BOUND BY IT, DO NOT OPEN THE PACKAGE AND/OR DOWNLOAD AND/OR INSTALL THE SOFTWARE AND PROMPTLY (at least within 7 days from the date you received this package) RETURN THE PRODUCTS TO THALES, ERASE THE SOFTWARE, AND ANY PART THEREOF, FROM YOUR COMPUTER AND DO NOT USE IT IN ANY MANNER WHATSOEVER.

This Agreement has 3 sections:

Section I applies if you are downloading or using the Product free of charge for evaluation purposes only.

Section II applies if you have purchased or have been otherwise granted by Thales a license to use the Product.

Section III applies to all grants of license.

## 1. SECTION I - TERMS APPLICABLE TO GRANT OF EVALUATION LICENSE

1.1 License Grant. Thales hereby grants to you, and you accept, a nonexclusive license to use the Product in machine-readable, object code form only, free of charge, for the purpose of evaluating whether to purchase an ongoing license to the Product and only as authorized in this License Agreement. The evaluation period is limited to the maximum amount of days specified in your applicable evaluation package. You may use the Product, during the evaluation period, in the manner described in Section III below under "Extent of Grant."

1.2 DISCLAIMER OF WARRANTY. The Product is provided on an "AS IS" basis, without warranty of any kind. IMPLIED WARRANTIES OF FITNESS FOR A PARTICULAR PURPOSE, SATISFACTION AND MERCHANTABILITY SHALL NOT APPLY. SOME JURISDICTIONS DO NOT ALLOW EXCLUSIONS OF AN IMPLIED WARRANTY, SO THIS DISCLAIMER MAY NOT APPLY TO YOU AND YOU MAY HAVE OTHER

**LEGAL RIGHTS THAT VARY BY JURISDICTION.** The entire risk as to the quality and performance of the Product is borne by you. This disclaimer of warranty constitutes an essential part of the agreement.

If you initially acquired a copy of the Product without purchasing a license and you wish to purchase a license, contact Thales or any Thales representative.

## 2. SECTION II - APPLICABLE TERMS WHEN GRANTED A LICENSE

**2.1 License Grant.** Subject to your payment of the license fees applicable to the type and amount of licenses purchased by you and set forth in your applicable purchase order, Thales hereby grants to you, and you accept, a personal, nonexclusive and fully revocable limited License to use the Software (as such term is defined in Section III hereunder, in the Intellectual Property subsection), in executable form only, as described in the Software accompanying user documentation and only according to the terms of this Agreement: (i) you may install the Software and use it on computers located in your place of business, as described in Thales's related documentation; (ii) you may merge and link the Software into your computer programs for the sole purpose described in the Sentinel LDK Software Protection and Licensing Guide; however, any portion of the Software merged into another computer program shall be deemed as derivative work and will continue to be subject to the terms of this Agreement; and (iii) you are permitted to make a reasonable number of copies of the Software solely for backup purposes. The Software shall not be used for any other purposes.

**2.2 Sub-Licensing.** After merging the Software in your computer program(s) according to the License Grant section above, you may sub-license, pursuant to the terms of this Agreement, the merged Software and resell the hardware components of the Product, which you purchased from Thales, if applicable, to distributors and/or users. Preceding such a sale and sub-licensing, you shall make sure that your contracts with any of your distributors and/or end users (and their contracts with their customers) shall contain warranties, disclaimers, limitation of liability, and license terms which are no less protective of Thales's rights than such equivalent provisions contained herein. In addition, you shall make it abundantly clear to your distributors and/or end users, that Thales is not and shall not, under any circumstances, be responsible or liable in any way for the software and software licenses contained in your computer programs which you merge with the Thales Software and distribute to your distributors and/or end users, including, without limitation, with respect to extending license terms and providing maintenance for any software elements and/or computer programs which are not the Thales Software. Thales expressly disclaims any responsibility and liability with respect to any computer programs, software elements, and/or hardware elements which are not and do not form part of the Thales product.

**2.3 Limited Warranty.** Thales warrants, for your benefit alone, that (i) the Software, when and as delivered to you, and for a period of three (3) months after the date of delivery to you, will perform in substantial compliance with the Sentinel LDK Software Protection and Licensing Guide, provided that it is used on the computer hardware and with the operating system for which it was designed; and (ii) that the Sentinel HL key and microSD card, for a period of twenty four (24) months after the date of delivery to you, will be substantially free from significant defects in materials and workmanship. You may enable or disable certain features when applying the Sentinel LDK protection software by changing settings in the Sentinel LDK tools in accordance with the Sentinel LDK Software

Protection and Licensing Guide; HOWEVER, IT IS IMPORTANT TO NOTE THAT WHEN ENABLING OR DISABLING SOME FEATURES YOU MIGHT REDUCE THE LEVEL OF PROTECTION PROVIDED BY THE SOFTWARE.



**2.4 Warranty Disclaimer.** THALES DOES NOT WARRANT THAT ANY OF ITS PRODUCT(S) WILL MEET YOUR REQUIREMENTS OR THAT THEIR OPERATION WILL BE UNINTERRUPTED OR ERROR-FREE. TO THE EXTENT ALLOWED BY LAW, THALES EXPRESSLY DISCLAIMS ALL EXPRESS WARRANTIES NOT STATED HERE AND ALL IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. NO THALES'S DEALER, DISTRIBUTOR, RESELLER, AGENT OR EMPLOYEE IS AUTHORIZED TO MAKE ANY

MODIFICATIONS, EXTENSIONS, OR ADDITIONS TO THIS WARRANTY. If any modifications are made to the Software or to any other part of the Product by you; if the media, the Sentinel key, or the microSD card is subjected to accident, abuse, or improper use; or if you violate any of the terms of this Agreement, then the warranty in Section 2.3 above, shall immediately be terminated. The warranty shall not apply if the Software is used on or in conjunction with hardware or program other than the unmodified version of hardware and program with which the Software was designed to be used as described in the Sentinel LDK Software Protection and Licensing Guide. The limited warranty does not cover any damage to the microSD card that results from improper installation, accident, abuse, misuse, natural disaster, insufficient or excessive electrical supply, abnormal mechanical or environmental conditions, or any unauthorized disassembly, repair or modification. This limited warranty shall not apply if: (i) the microSD card was not used in accordance with any accompanying instructions, or (ii) the product was not used for its intended function. This limited warranty also does not apply to any microSD card on which the original identification information has been altered, obliterated or removed, that has not been handled or packaged correctly, that has been sold as second-hand or that has been resold contrary to U.S. and other applicable export regulations.

**2.5 Limitation of Remedies.** In the event of a breach of the warranty set forth above, Thales's sole obligation, and your sole remedy shall be, at Thales's sole discretion: (i) to replace or repair the Product, or component thereof, that does not meet the foregoing limited warranty, free of charge; or (ii) to refund the price paid by you for the Product, or component thereof. Any replacement or repaired component will be warranted for the remainder of the original warranty period or 30 days, whichever is longer. Warranty claims must be made in writing during the warranty period and within seven (7) days of the observation of the defect accompanied by evidence satisfactory to Thales. All Products should be returned to the distributor from which they were purchased (if not purchased directly from Thales) and shall be shipped by the returning party with freight and insurance paid. The Product or component thereof must be returned with a copy of your receipt. Thales is not liable for, and does not cover under warranty, any damages or losses of any kind whatsoever resulting from loss of, damage to or corruption of, content or data or any costs associated with determining the source of system problems or removing, servicing or installing the microSD card. This warranty excludes third party software, connected equipment or stored data. Thales is therefore not liable for any losses or damage attributable to third party software, connected equipment or stored data. In the event of a claim, Thales's sole obligation shall be to issue a refund or replacement of the microSD card.

### 3. SECTION III - TERMS APPLICABLE TO ALL GRANTS OF LICENSE

**3.1 Extent of Grant and Prohibited Uses.** Except as specifically permitted in Sections 2.1 and 2.2 above, you agree not to (i) use the Product in any manner beyond the scope of license purchased by you in accordance with your applicable purchase order; (ii) use, modify, merge or sub-license the Software or any other of Thales's products except as expressly authorized in this Agreement and in the Sentinel LDK Software Protection and Licensing Guide; and (iii) sell, license (or sub-license), lease, assign, transfer, pledge, or share your rights under

this License with/to anyone else; and (iv) modify, disassemble, decompile, reverse engineer, revise or enhance the Software or attempt to discover the Software's source code; and (v) place the Software onto a server so that it is accessible via a public network; and (vi) use any back-up or archival copies of the Software (or allow someone else to use such copies) for any purpose other than to replace an original copy if it is destroyed or becomes defective. If you are a member of the European Union, this agreement does not affect your rights under any legislation implementing the EC Council Directive on the Legal Protection of Computer Programs. If you seek any information within the meaning of that Directive you should initially approach Thales.

**3.2 Intellectual Property.** THIS IS A LICENSE AGREEMENT AND NOT AN AGREEMENT FOR SALE. The software component of the Sentinel LDK Product, including any revisions, corrections, modifications, enhancements, updates and/or upgrades thereto, (hereinafter in whole or any part thereof defined as: "Software"), and the related documentation, ARE NOT FOR SALE and are and shall remain in Thales's sole property. All intellectual property rights (including, without limitation, copyrights, patents, trade secrets, trademarks, etc.) evidenced by or embodied in and/or attached/connected/related to the Product, (including, without limitation, the Software code and the work product performed in accordance with Section II above) are and shall be owned solely by Thales. This License Agreement does not convey to you an interest in or to the Software but only a limited right of use revocable in accordance with the terms of this License Agreement. Nothing in this Agreement constitutes a waiver of Thales's intellectual property rights under any law.

**3.3 Audit.** Thales shall have the right, at its own expense, upon reasonable prior notice, to periodically inspect and audit your records to ensure your compliance with the terms and conditions of this license agreement.

**3.4 Termination.** Without prejudice to any other rights, Thales may terminate this license upon the breach by you of any term hereof. Upon such termination by Thales, you agree to destroy, or return to Thales, the Product and the Documentation and all copies and portions thereof.

**3.5 Limitation of Liability.** Thales's cumulative liability to you or any other party for any loss or damages resulting from any claims, demands, or actions arising out of or relating to this Agreement and/or the use of the Product shall not exceed the license fee paid to Thales for the use of the Product/s that gave rise to the action or claim, and if no such Product/s is/are so applicable then Thales's liability shall not exceed the amount of license fees paid by You to Thales hereunder during the twelve (12) months period preceding the event. UNDER NO CIRCUMSTANCES AND UNDER NO LEGAL THEORY, TORT, CONTRACT, OR OTHERWISE, SHALL THALES OR ITS SUPPLIERS OR RESELLERS OR AGENTS BE LIABLE TO YOU OR ANY OTHER PERSON FOR ANY INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES OF ANY TYPE INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF GOODWILL, BUSINESS INTERRUPTION, COMPUTER FAILURE OR MALFUNCTION, LOSS OF BUSINESS PROFITS, LOSS OF BUSINESS INFORMATION, DAMAGES FOR PERSONAL INJURY OR ANY AND ALL OTHER COMMERCIAL DAMAGES OR LOSSES, EVEN IF THALES SHALL HAVE BEEN INFORMED OF THE POSSIBILITY OF SUCH DAMAGES, OR FOR ANY CLAIM BY ANY OTHER PARTY. SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THIS LIMITATION AND EXCLUSION MAY NOT APPLY TO YOU.

**3.6 No other Warranties.** Except and to the extent specifically provided herein, Thales makes no warranty or representation, either express or implied, with respect to its Products as, including their quality, performance, merchantability or fitness for a particular purpose.

**3.7 Export Controls.** YOU ACKNOWLEDGE THAT THE SOFTWARE IS SUBJECT TO REGULATION BY UNITED STATES, EUROPEAN UNION, AND/OR OTHER GOVERNMENT AGENCIES, WHICH PROHIBIT EXPORT OR DIVERSION OF THE SOFTWARE TO CERTAIN COUNTRIES AND CERTAIN PERSONS. YOU AGREE TO COMPLY WITH ALL EXPORT LAWS, REGULATIONS AND RESTRICTIONS OF THE UNITED STATES DEPARTMENT OF STATE, DEPARTMENT OF COMMERCE OR OTHER LEGAL AUTHORITY WITHIN THE UNITED STATES OR ANY FOREIGN ENTITY WHICH REGULATES THEIR SHIPMENT. YOU WILL NOT EXPORT IN ANY MANNER, EITHER DIRECTLY OR INDIRECTLY, ANY SOFTWARE OR ANY PRODUCT THAT INCORPORATES ANY SOFTWARE WITHOUT FIRST OBTAINING ALL NECESSARY APPROVAL FROM APPROPRIATE GOVERNMENT AGENCIES. YOU AGREE TO INDEMNIFY THALES AGAINST ALL CLAIMS, LOSSES, DAMAGES, LIABILITIES, COSTS AND EXPENSES, INCLUDING REASONABLE ATTORNEYS' FEES, TO THE EXTENT SUCH CLAIMS ARISE OUT OF ANY BREACH OF THIS SECTION 3.7.

**3.8 Governing Law & Jurisdiction.** This License Agreement shall be construed, interpreted and governed by the laws of the State of Delaware without regard to conflicts of laws and provisions thereof. The exclusive forum for any disputes arising out of or relating to this License Agreement shall be an appropriate federal or state court sitting in Harford County, State of Maryland, USA. The application of the United Nations Convention of Contracts for the International Sale of Goods is expressly excluded. The failure of either party to enforce any rights granted hereunder or to take action against the other party in the event of any breach hereunder shall not be deemed a waiver by that party as to subsequent enforcement of rights or subsequent actions in the event of future breaches.

**3.9 Third Party Software.** If distributed, the Software is distributed with open source software components ("Open Source Software Components" or "OSS") and other third party software (such OSS and other third party software individually or collectively referred to herein as "Third Party Software"), which are provided "As Is" without any warranty of any kind and subject to their own applicable license agreements (which might also contain limited warranties and liabilities) referenced in Exhibit A (for the Software aside from that included in Sentinel LDK-EMS) and Exhibit B (for the Software included in Sentinel LDK-EMS). THOSE TERMS AND CONDITIONS SPECIFIED FOR EACH SPECIFIC OPEN SOURCE SOFTWARE COMPONENT OR OTHER THIRD PARTY SOFTWARE SHALL BE APPLICABLE TO SUCH COMPONENT. Third Party Software in addition to those listed in Exhibit A and B may be added to the Software from time to time, and will also be subject to their own applicable license agreements. Each Open Source Software Component or other third party software is copyrighted by its respective copyright owner(s) as indicated in the applicable copyright notices which can be found in the applicable license, installation, readme and/or help files for such Open Source Software Components or other third party software. Thales makes no representations or warranties with regard to the Open Source Software Components or other third party software. If the Software contains any Third Party Software other than the ones listed in Exhibit A and B, such Third Party Software is also provided "As Is" without any warranty of any kind and shall be subject to the terms and conditions as set forth in the agreements contained/attached to such Third Party Software. In the event such agreements are not available, such Third Party Software is provided "As Is" without any warranty of any kind and shall be used in accordance with this Agreement.

**3.10 Miscellaneous.** If the copy of the Product you received was accompanied by a printed or other form of "hard-copy" End User License Agreement whose terms vary from this Agreement, then the hard-copy End User License Agreement governs your use of the Product. This Agreement represents the complete agreement

concerning this license and may be amended only by a writing executed by both parties. THE ACCEPTANCE OF ANY PURCHASE ORDER PLACED BY YOU, IS EXPRESSLY MADE CONDITIONAL ON YOUR ASSENT TO THE TERMS SET FORTH HEREIN, COMBINED WITH THE APPLICABLE LICENSE SCOPE AND TERMS, IF ANY, SET FORTH IN YOUR PURCHASE ORDER. If any provision of this Agreement is held to be unenforceable, such provision shall be reformed only to the extent necessary to make it enforceable. The failure of either party to enforce any rights granted hereunder or to take action against the other party in the event of any breach hereunder shall not be deemed a waiver by that party as to subsequent enforcement of rights or subsequent actions in the event of future breaches.

Copyright © 2022 Thales Group. All rights reserved.

# Exhibit A - Third-Party Software

Open SSL

Version 1.1.1l

Copyright (c) 1998-2018 The OpenSSL Project. All rights reserved.

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com). This product includes software written by Tim Hudson (tjh@cryptsoft.com).

/\* =====

Copyright (c) 1998-2018 The OpenSSL Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgment:

"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit.  
(<http://www.openssl.org/>)"

4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [openssl-core@openssl.org](mailto:openssl-core@openssl.org).
5. Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project.
6. Redistributions of any form whatsoever must retain the following acknowledgment:

"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit  
(<http://www.openssl.org/>)"

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,

EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

=====

This product includes cryptographic software written by Eric Young (eay@cryptsoft.com). This product includes software written by Tim Hudson (tjh@cryptsoft.com).

Original SSLeay License

Version 1.0.2u

Copyright (c) 1995-1998 The OpenSSL Project. All rights reserved.

This product includes software written by Tim Hudson (tjh@cryptsoft.com)

-----

Copyright (C) 1995-1998 Eric Young (eay@cryptsoft.com)

All rights reserved.

This package is an SSL implementation written by Eric Young (eay@cryptsoft.com).

The implementation was written so as to conform with Netscapes SSL.

This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@cryptsoft.com).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed.

If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used. This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:

"This product includes cryptographic software written by Eric Young (eay@cryptsoft.com)"

The word 'cryptographic' can be left out if the routines from the library being used are not cryptographic related :-).

4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement:

"This product includes software written by Tim Hudson (tjh@cryptsoft.com)"

THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The license and distribution terms for any publically available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution license [including the GNU Public License.]

LLVM

Version 12.0.0

Copyright (c) 2003-2019 University of Illinois at Urbana-Champaign.

The LLVM Project is under the Apache License v2.0 with LLVM Exceptions:

=====

Apache License

Version 2.0, January 2004

<http://www.apache.org/licenses/>

TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

1. Definitions.

"License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common

control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner



or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution." "Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work

or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

- (a) You must give any other recipients of the Work or Derivative Works a copy of this License; and
- (b) You must cause any modified files to carry prominent notices stating that You changed the files; and
- (c) You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and
- (d) If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution

notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License.

You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions.

Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.

7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any

risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

## END OF TERMS AND CONDITIONS

APPENDIX: How to apply the Apache License to your work.

To apply the Apache License to your work, attach the following boilerplate notice, with the fields enclosed by brackets "[ ]" replaced with your own identifying information. (Don't include the brackets!) The text should be enclosed in the appropriate comment syntax for the file format. We also recommend that a

file or class name and description of purpose be included on the same "printed page" as the copyright notice for easier identification within third-party archives.

Copyright [yyyy] [name of copyright owner]

Licensed under the Apache License, Version 2.0 (the "License");

you may not use this file except in compliance with the License.

You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software

distributed under the License is distributed on an "AS IS" BASIS,

WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.

See the License for the specific language governing permissions and

limitations under the License.

---- LLVM Exceptions to the Apache 2.0 License ----

As an exception, if, as a result of your compiling your source code, portions of this Software are embedded into an Object form of such source code, you may redistribute such embedded portions in such Object form without complying with the conditions of Sections 4(a), 4(b) and 4(d) of the License.

In addition, if you combine or link compiled forms of this Software with software that is licensed under the GPLv2 ("Combined Software") and if a court of competent jurisdiction determines that the patent provision (Section 3), the indemnity provision (Section 9) or other Section of the License conflicts with the conditions of the GPLv2, you may retroactively and prospectively choose to deem waived or otherwise exclude such Section(s) of the License, but only in their entirety and only with respect to the Combined Software.

=====

Software from third parties included in the LLVM Project:

=====

The LLVM Project contains third party software which is under different license terms. All such code will be identified clearly using at least one of two mechanisms:

- 1) It will be in a separate directory tree with its own `LICENSE.txt` or `LICENSE` file at the top containing the specific license and restrictions which apply to that software, or
- 2) It will contain specific license and restriction terms at the top of every file.

=====

Legacy LLVM License (<https://llvm.org/docs/DeveloperPolicy.html#legacy>):

=====

University of Illinois/NCSA

Open Source License

Copyright (c) 2003-2019 University of Illinois at Urbana-Champaign.

All rights reserved.

Developed by:

LLVM Team

University of Illinois at Urbana-Champaign

<http://llvm.org>

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal with the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

\* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimers.

\* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimers in the documentation and/or other materials provided with the distribution.

\* Neither the names of the LLVM Team, University of Illinois at Urbana-Champaign, nor the names of its contributors may be used to endorse or promote products derived from this Software without specific prior written permission.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

TAGGANT

Version 1.0

Copyright (c) 2012 IEEE. All rights reserved

-----

This software was developed by The Institute of Electrical and Electronics Engineers, Incorporated (IEEE), through the Industry Connections Security Group (ICSG) of its Standards Association. Portions of it include software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>), and those portions are governed by the OpenSSL Toolkit License.

IEEE License

=====

Copyright (c) 2012 IEEE. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgment:

"This product includes software developed by the IEEE Industry Connections Security Group (ICSG)".

4. The name "IEEE" must not be used to endorse or promote products derived from this software without prior written permission from the IEEE Standards Association ([stds.ipr@ieee.org](mailto:stds.ipr@ieee.org)).
5. Products derived from this software may not contain "IEEE" in their names without prior written permission from the IEEE Standards Association ([stds.ipr@ieee.org](mailto:stds.ipr@ieee.org)).
6. Redistributions of any form whatsoever must retain the following acknowledgment:

"This product includes software developed by the IEEE Industry Connections Security Group (ICSG)".

THIS SOFTWARE IS PROVIDED "AS IS" AND "WITH ALL FAULTS." IEEE AND ITS CONTRIBUTORS EXPRESSLY DISCLAIM ALL WARRANTIES AND REPRESENTATIONS, EXPRESS OR IMPLIED, INCLUDING, WITHOUT LIMITATION: (A) THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE; (B) ANY WARRANTY OF NON-INFRINGEMENT; AND (C) ANY WARRANTY WITH RESPECT TO THE QUALITY, ACCURACY, EFFECTIVENESS, CURRENCY OR COMPLETENESS OF THE SOFTWARE.

IN NO EVENT SHALL IEEE OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES, (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE AND REGARDLESS OF WHETHER SUCH DAMAGE WAS FORESEEABLE.

THIS SOFTWARE USES STRONG CRYPTOGRAPHY, WHICH MAY BE SUBJECT TO LAWS AND REGULATIONS GOVERNING ITS USE, EXPORTATION OR IMPORTATION. YOU ARE SOLELY RESPONSIBLE FOR COMPLYING WITH ALL APPLICABLE LAWS AND REGULATIONS, INCLUDING, BUT NOT LIMITED TO, ANY THAT GOVERN YOUR USE, EXPORTATION OR IMPORTATION OF THIS SOFTWARE. IEEE AND ITS CONTRIBUTORS DISCLAIM ALL LIABILITY ARISING FROM YOUR USE OF THE SOFTWARE IN VIOLATION OF ANY APPLICABLE LAWS OR REGULATIONS.

=====

#### OpenSSL Toolkit License

=====

The OpenSSL toolkit stays under a dual license, i.e. both the conditions of the OpenSSL License and the original SSLeay license apply to the toolkit.

See below for the actual license texts. Actually both licenses are BSD-style Open Source licenses. In case of any license issues related to OpenSSL please contact [openssl-core@openssl.org](mailto:openssl-core@openssl.org).

#### OpenSSL License

-----

=====

Copyright (c) 1998-2011 The OpenSSL Project. All rights reserved.



Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgment:

"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit.  
(<http://www.openssl.org/>)"

4. The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [openssl-core@openssl.org](mailto:openssl-core@openssl.org).

5. Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project.

6. Redistributions of any form whatsoever must retain the following acknowledgment:

"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit  
(<http://www.openssl.org/>)"

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

=====

This product includes cryptographic software written by Eric Young ([eay@cryptsoft.com](mailto:eay@cryptsoft.com)). This product includes software written by Tim Hudson ([tjh@cryptsoft.com](mailto:tjh@cryptsoft.com)).

Original SSLeay License

-----

Copyright (C) 1995-1998 Eric Young ([eay@cryptsoft.com](mailto:eay@cryptsoft.com))

All rights reserved.

This package is an SSL implementation written by Eric Young (eay@cryptsoft.com).

The implementation was written so as to conform with Netscapes SSL.

This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@cryptsoft.com).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed.

If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used.

This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:

"This product includes cryptographic software written by Eric Young (eay@cryptsoft.com)"

The word 'cryptographic' can be left out if the routines from the library being used are not cryptographic related :-).

4. If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement:

"This product includes software written by Tim Hudson (tjh@cryptsoft.com)"

THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER

CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The license and distribution terms for any publically available version or derivative of this code cannot be changed. i.e. this code cannot simply be copied and put under another distribution license [including the GNU Public License.]

smali/baksmali

Version 2.2.4

Copyright (c) 2010 Ben Gruver (JesusFreke)

\*\*\*\*\*

Copyright (c) 2010 Ben Gruver (JesusFreke)

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

\*\*\*\*\*

Unless otherwise stated in the code/commit message, any changes with the committer of bgruv@google.com is copyrighted by Google Inc. and released under the following license:

\*\*\*\*\*

Copyright 2011, Google Inc.

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

\* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

\* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

\* Neither the name of Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

\*\*\*\*\*

Various portions of the code are taken from the Android Open Source Project, and are used in accordance with the following license:

\*\*\*\*\*

Copyright (C) 2007 The Android Open Source Project

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License.

You may obtain a copy of the License at <http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.

See the License for the specific language governing permissions and limitations under the License.

\*\*\*\*\*

Some parts of the smalidea plugin are based on code from the IDEA project, per the following license

\*\*\*\*\*

Copyright 2000-2014 JetBrains s.r.o.

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License.

You may obtain a copy of the License at <http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.

See the License for the specific language governing permissions and limitations under the License.

\*\*\*\*\*

## Zlib

Version: 1.2.11

Copyright notice: (C) 1995-2017 Jean-loup Gailly and Mark Adler

This software is provided 'as-is', without any express or implied warranty. In no event will the authors be held liable for any damages arising from the use of this software.

Permission is granted to anyone to use this software for any purpose, including commercial applications, and to alter it and redistribute it freely, subject to the following restrictions:

1. The origin of this software must not be misrepresented; you must not claim that you wrote the original software. If you use this software in a product, an acknowledgment in the product documentation would be appreciated but is not required.
2. Altered source versions must be plainly marked as such, and must not be misrepresented as being the original software.
3. This notice may not be removed or altered from any source distribution.

## Expat

Version: 2.4.7

Copyright (c) 1998 - 2000 Thai Open Source Software Center Ltd and Clark Cooper

Copyright (c) 2001-2022 Expat maintainers.

## MIT License

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT.

IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Trio

Version: 1.16

Copyright (C) 1998-2001 by Bjorn Reese and Daniel Stenberg.

Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

THIS SOFTWARE IS PROVIDED ``AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE AUTHORS AND CONTRIBUTORS ACCEPT NO RESPONSIBILITY IN ANY CONCEIVABLE MANNER.

Y2038

Copyright (c) 2007-2010 Michael G Schwern

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Libtommath

Version: 0.42

Copyright: Copyright © Tom St Denis

[LICENSE #1]

LibTomMath is public domain.

BeaEngine 5

Copyright (C) 2007 Free Software Foundation, Inc. <<http://fsf.org/>>

GNU LESSER GENERAL PUBLIC LICENSE

Version 3, 29 June 2007

Copyright (C) 2007 Free Software Foundation, Inc. <<http://fsf.org/>>

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

This version of the GNU Lesser General Public License incorporates the terms and conditions of version 3 of the GNU General Public License, supplemented by the additional permissions listed below.

#### 0. Additional Definitions.

As used herein, "this License" refers to version 3 of the GNU Lesser General Public License, and the "GNU GPL" refers to version 3 of the GNU General Public License.

"The Library" refers to a covered work governed by this License, other than an Application or a Combined Work as defined below.

An "Application" is any work that makes use of an interface provided by the Library, but which is not otherwise based on the Library.

Defining a subclass of a class defined by the Library is deemed a mode of using an interface provided by the Library.

A "Combined Work" is a work produced by combining or linking an Application with the Library. The particular version of the Library with which the Combined Work was made is also called the "Linked Version".

The "Minimal Corresponding Source" for a Combined Work means the Corresponding Source for the Combined Work, excluding any source code for portions of the Combined Work that, considered in isolation, are based on the Application, and not on the Linked Version.

The "Corresponding Application Code" for a Combined Work means the object code and/or source code for the Application, including any data and utility programs needed for reproducing the Combined Work from the Application, but excluding the System Libraries of the Combined Work.

#### 1. Exception to Section 3 of the GNU GPL.

You may convey a covered work under sections 3 and 4 of this License without being bound by section 3 of the GNU GPL.

#### 2. Conveying Modified Versions.

If you modify a copy of the Library, and, in your modifications, a facility refers to a function or data to be supplied by an Application that uses the facility (other than as an argument passed when the facility is invoked), then you may convey a copy of the modified version:

a) under this License, provided that you make a good faith effort to ensure that, in the event an Application does not supply the function or data, the facility still operates, and performs whatever part of its purpose remains meaningful, or b) under the GNU GPL, with none of the additional permissions of this License applicable to that copy.

### 3. Object Code Incorporating Material from Library Header Files.

The object code form of an Application may incorporate material from a header file that is part of the Library. You may convey such object code under terms of your choice, provided that, if the incorporated material is not limited to numerical parameters, data structure layouts and accessors, or small macros, inline functions and templates (ten or fewer lines in length), you do both of the following:

- a) Give prominent notice with each copy of the object code that the Library is used in it and that the Library and its use are covered by this License.
- b) Accompany the object code with a copy of the GNU GPL and this license document.

### 4. Combined Works.

You may convey a Combined Work under terms of your choice that, taken together, effectively do not restrict modification of the portions of the Library contained in the Combined Work and reverse engineering for debugging such modifications, if you also do each of the following:

- a) Give prominent notice with each copy of the Combined Work that the Library is used in it and that the Library and its use are covered by this License.
- b) Accompany the Combined Work with a copy of the GNU GPL and this license document.
- c) For a Combined Work that displays copyright notices during execution, include the copyright notice for the Library among these notices, as well as a reference directing the user to the copies of the GNU GPL and this license document.
- d) Do one of the following:
  - 0) Convey the Minimal Corresponding Source under the terms of this License, and the Corresponding Application Code in a form suitable for, and under terms that permit, the user to recombine or relink the Application with a modified version of the Linked Version to produce a modified Combined Work, in the manner specified by section 6 of the GNU GPL for conveying Corresponding Source.
  - 1) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (a) uses at run time a copy of the Library already present on the user's computer system, and (b) will operate properly with a modified version of the Library that is interface-compatible with the Linked Version.
- e) Provide Installation Information, but only if you would otherwise be required to provide such information under section 6 of the GNU GPL, and only to the extent that such information is necessary to install and execute a modified version of the Combined Work produced by recombining or relinking the Application with a modified version of the Linked Version. (If you use option 4d0, the Installation Information must accompany the Minimal



Corresponding Source and Corresponding Application Code. If you use option 4d1, you must provide the Installation Information in the manner specified by section 6 of the GNU GPL for conveying Corresponding Source.)

#### 5. Combined Libraries.

You may place library facilities that are a work based on the Library side by side in a single library together with other library facilities that are not Applications and are not covered by this License, and convey such a combined library under terms of your choice, if you do both of the following:

- a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities, conveyed under the terms of this License.
- b) Give prominent notice with the combined library that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.

#### 6. Revised Versions of the GNU Lesser General Public License.

The Free Software Foundation may publish revised and/or new versions of the GNU Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library as you received it specifies that a certain numbered version of the GNU Lesser General Public License "or any later version" applies to it, you have the option of following the terms and conditions either of that published version or of any later version published by the Free Software Foundation. If the Library as you received it does not specify a version number of the GNU Lesser General Public License, you may choose any version of the GNU Lesser General Public License ever published by the Free Software Foundation.

If the Library as you received it specifies that a proxy can decide whether future versions of the GNU Lesser General Public License shall apply, that proxy's public statement of acceptance of any version is permanent authorization for you to choose that version for the Library.

### GNU GENERAL PUBLIC LICENSE

Version 3, 29 June 2007

Copyright (C) 2007 Free Software Foundation, Inc. <<http://fsf.org/>>

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### Preamble

The GNU General Public License is a free, copyleft license for software and other kinds of works.

The licenses for most software and other practical works are designed to take away your freedom to share and change the works. By contrast, the GNU General Public License is intended to guarantee your freedom to share

and change all versions of a program--to make sure it remains free software for all its users. We, the Free Software Foundation, use the GNU General Public License for most of our software; it applies also to any other work released this way by its authors. You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for them if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs, and that you know you can do these things.

To protect your rights, we need to prevent others from denying you these rights or asking you to surrender the rights. Therefore, you have certain responsibilities if you distribute copies of the software, or if you modify it: responsibilities to respect the freedom of others.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must pass on to the recipients the same freedoms that you received. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

Developers that use the GNU GPL protect your rights with two steps: (1) assert copyright on the software, and (2) offer you this License giving you legal permission to copy, distribute and/or modify it.

For the developers' and authors' protection, the GPL clearly explains that there is no warranty for this free software. For both users' and authors' sake, the GPL requires that modified versions be marked as changed, so that their problems will not be attributed erroneously to authors of previous versions.

Some devices are designed to deny users access to install or run modified versions of the software inside them, although the manufacturer can do so. This is fundamentally incompatible with the aim of protecting users' freedom to change the software. The systematic pattern of such abuse occurs in the area of products for individuals to use, which is precisely where it is most unacceptable. Therefore, we have designed this version of the GPL to prohibit the practice for those products. If such problems arise substantially in other domains, we stand ready to extend this provision to those domains in future versions of the GPL, as needed to protect the freedom of users.

Finally, every program is threatened constantly by software patents. States should not allow patents to restrict development and use of software on general-purpose computers, but in those that do, we wish to avoid the special danger that patents applied to a free program could make it effectively proprietary. To prevent this, the GPL assures that patents cannot be used to render the program non-free.

The precise terms and conditions for copying, distribution and modification follow.

## TERMS AND CONDITIONS

### 0. Definitions.

“This License” refers to version 3 of the GNU General Public License.

“Copyright” also means copyright-like laws that apply to other kinds of works, such as semiconductor masks.

“The Program” refers to any copyrightable work licensed under this License. Each licensee is addressed as “you”. “Licensees” and “recipients” may be individuals or organizations.

To “modify” a work means to copy from or adapt all or part of the work in a fashion requiring copyright permission, other than the making of an exact copy. The resulting work is called a “modified version” of the earlier work or a work “based on” the earlier work.

A “covered work” means either the unmodified Program or a work based on the Program.

To “propagate” a work means to do anything with it that, without permission, would make you directly or secondarily liable for infringement under applicable copyright law, except executing it on a computer or modifying a private copy. Propagation includes copying, distribution (with or without modification), making available to the public, and in some countries other activities as well.

To “convey” a work means any kind of propagation that enables other parties to make or receive copies. Mere interaction with a user through a computer network, with no transfer of a copy, is not conveying.

An interactive user interface displays “Appropriate Legal Notices” to the extent that it includes a convenient and prominently visible feature that (1) displays an appropriate copyright notice, and (2) tells the user that there is no warranty for the work (except to the extent that warranties are provided), that licensees may convey the work under this License, and how to view a copy of this License. If the interface presents a list of user commands or options, such as a menu, a prominent item in the list meets this criterion.

#### 1. Source Code.

The “source code” for a work means the preferred form of the work for making modifications to it. “Object code” means any non-source form of a work.

A “Standard Interface” means an interface that either is an official standard defined by a recognized standards body, or, in the case of interfaces specified for a particular programming language, one that is widely used among developers working in that language.

The “System Libraries” of an executable work include anything, other than the work as a whole, that (a) is included in the normal form of packaging a Major Component, but which is not part of that Major Component, and (b) serves only to enable use of the work with that Major Component, or to implement a Standard Interface for which an implementation is available to the public in source code form. A “Major Component”, in this context, means a major essential component (kernel, window system, and so on) of the specific operating system (if any) on which the executable work runs, or a compiler used to produce the work, or an object code interpreter used to run it.

The “Corresponding Source” for a work in object code form means all the source code needed to generate, install, and (for an executable work) run the object code and to modify the work, including scripts to control those activities. However, it does not include the work’s System Libraries, or general-purpose tools or generally available free programs which are used unmodified in performing those activities but which are not part of the work. For example, Corresponding Source includes interface definition files associated with source files for the work, and the source code for shared libraries and dynamically linked subprograms that the work is specifically designed to require, such as by intimate data communication or control flow between those subprograms and other parts of the work.

The Corresponding Source need not include anything that users can regenerate automatically from other parts of the Corresponding Source.

The Corresponding Source for a work in source code form is that same work.

## 2. Basic Permissions.

All rights granted under this License are granted for the term of copyright on the Program, and are irrevocable provided the stated conditions are met. This License explicitly affirms your unlimited permission to run the unmodified Program. The output from running a covered work is covered by this License only if the output, given its content, constitutes a covered work. This License acknowledges your rights of fair use or other equivalent, as provided by copyright law.

You may make, run and propagate covered works that you do not convey, without conditions so long as your license otherwise remains in force. You may convey covered works to others for the sole purpose of having them make modifications exclusively for you, or provide you with facilities for running those works, provided that you comply with the terms of this License in conveying all material for which you do not control copyright. Those thus making or running the covered works for you must do so exclusively on your behalf, under your direction and control, on terms that prohibit them from making any copies of your copyrighted material outside their relationship with you.

Conveying under any other circumstances is permitted solely under the conditions stated below. Sublicensing is not allowed; section 10 makes it unnecessary.

## 3. Protecting Users' Legal Rights From Anti-Circumvention Law.

No covered work shall be deemed part of an effective technological measure under any applicable law fulfilling obligations under article 11 of the WIPO copyright treaty adopted on 20 December 1996, or similar laws prohibiting or restricting circumvention of such measures.

When you convey a covered work, you waive any legal power to forbid circumvention of technological measures to the extent such circumvention is effected by exercising rights under this License with respect to the covered work, and you disclaim any intention to limit operation or modification of the work as a means of enforcing, against the work's users, your or third parties' legal rights to forbid circumvention of technological measures.

## 4. Conveying Verbatim Copies.

You may convey verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice; keep intact all notices stating that this License and any non-permissive terms added in accord with section 7 apply to the code; keep intact all notices of the absence of any warranty; and give all recipients a copy of this License along with the Program.

You may charge any price or no price for each copy that you convey, and you may offer support or warranty protection for a fee.

## 5. Conveying Modified Source Versions.

You may convey a work based on the Program, or the modifications to produce it from the Program, in the form of source code under the terms of section 4, provided that you also meet all of these conditions:

- a) The work must carry prominent notices stating that you modified it, and giving a relevant date.

- b) The work must carry prominent notices stating that it is released under this License and any conditions added under section 7. This requirement modifies the requirement in section 4 to “keep intact all notices”.
- c) You must license the entire work, as a whole, under this License to anyone who comes into possession of a copy. This License will therefore apply, along with any applicable section 7 additional terms, to the whole of the work, and all its parts, regardless of how they are packaged. This License gives no permission to license the work in any other way, but it does not invalidate such permission if you have separately received it.
- d) If the work has interactive user interfaces, each must display Appropriate Legal Notices; however, if the Program has interactive interfaces that do not display Appropriate Legal Notices, your work need not make them do so.

A compilation of a covered work with other separate and independent works, which are not by their nature extensions of the covered work, and which are not combined with it such as to form a larger program, in or on a volume of a storage or distribution medium, is called an “aggregate” if the compilation and its resulting copyright are not used to limit the access or legal rights of the compilation's users beyond what the individual works permit. Inclusion of a covered work in an aggregate does not cause this License to apply to the other parts of the aggregate.

## 6. Conveying Non-Source Forms.

You may convey a covered work in object code form under the terms of sections 4 and 5, provided that you also convey the machine-readable Corresponding Source under the terms of this License, in one of these ways:

- a) Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by the Corresponding Source fixed on a durable physical medium customarily used for software interchange.
- b) Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by a written offer, valid for at least three years and valid for as long as you offer spare parts or customer support for that product model, to give anyone who possesses the object code either (1) a copy of the Corresponding Source for all the software in the product that is covered by this License, on a durable physical medium customarily used for software interchange, for a price no more than your reasonable cost of physically performing this conveying of source, or (2) access to copy the Corresponding Source from a network server at no charge.
- c) Convey individual copies of the object code with a copy of the written offer to provide the Corresponding Source. This alternative is allowed only occasionally and noncommercially, and only if you received the object code with such an offer, in accord with subsection 6b.
- d) Convey the object code by offering access from a designated place (gratis or for a charge), and offer equivalent access to the Corresponding Source in the same way through the same place at no further charge. You need not require recipients to copy the Corresponding Source along with the object code. If the place to copy the object code is a network server, the Corresponding Source may be on a different server (operated by you or a third party) that supports equivalent copying facilities, provided you maintain clear directions next to the object code saying where to find the Corresponding Source. Regardless of what server hosts the Corresponding Source, you remain obligated to ensure that it is available for as long as needed to satisfy these requirements.

e) Convey the object code using peer-to-peer transmission, provided you inform other peers where the object code and Corresponding Source of the work are being offered to the general public at no charge under subsection 6d.

A separable portion of the object code, whose source code is excluded from the Corresponding Source as a System Library, need not be included in conveying the object code work.

A “User Product” is either (1) a “consumer product”, which means any tangible personal property which is normally used for personal, family, or household purposes, or (2) anything designed or sold for incorporation into a dwelling. In determining whether a product is a consumer product, doubtful cases shall be resolved in favor of coverage. For a particular product received by a particular user, “normally used” refers to a typical or common use of that class of product, regardless of the status of the particular user or of the way in which the particular user actually uses, or expects or is expected to use, the product. A product is a consumer product regardless of whether the product has substantial commercial, industrial or non-consumer uses, unless such uses represent the only significant mode of use of the product.

“Installation Information” for a User Product means any methods, procedures, authorization keys, or other information required to install and execute modified versions of a covered work in that User Product from a modified version of its Corresponding Source. The information must suffice to ensure that the continued functioning of the modified object code is in no case prevented or interfered with solely because modification has been made.

If you convey an object code work under this section in, or with, or specifically for use in, a User Product, and the conveying occurs as part of a transaction in which the right of possession and use of the User Product is transferred to the recipient in perpetuity or for a fixed term (regardless of how the transaction is characterized), the Corresponding Source conveyed under this section must be accompanied by the Installation Information. But this requirement does not apply if neither you nor any third party retains the ability to install modified object code on the User Product (for example, the work has been installed in ROM).

The requirement to provide Installation Information does not include a requirement to continue to provide support service, warranty, or updates for a work that has been modified or installed by the recipient, or for the User Product in which it has been modified or installed. Access to a network may be denied when the modification itself materially and adversely affects the operation of the network or violates the rules and protocols for communication across the network.

Corresponding Source conveyed, and Installation Information provided, in accord with this section must be in a format that is publicly documented (and with an implementation available to the public in source code form), and must require no special password or key for unpacking, reading or copying.

## 7. Additional Terms.

“Additional permissions” are terms that supplement the terms of this License by making exceptions from one or more of its conditions. Additional permissions that are applicable to the entire Program shall be treated as though they were included in this License, to the extent that they are valid under applicable law. If additional permissions apply only to part of the Program, that part may be used separately under those permissions, but the entire Program remains governed by this License without regard to the additional permissions.

When you convey a copy of a covered work, you may at your option remove any additional permissions from that copy, or from any part of it. (Additional permissions may be written to require their own removal in certain cases when you modify the work.) You may place additional permissions on material, added by you to a covered work, for which you have or can give appropriate copyright permission.

Notwithstanding any other provision of this License, for material you add to a covered work, you may (if authorized by the copyright holders of that material) supplement the terms of this License with terms:

- a) Disclaiming warranty or limiting liability differently from the terms of sections 15 and 16 of this License; or
- b) Requiring preservation of specified reasonable legal notices or author attributions in that material or in the Appropriate Legal Notices displayed by works containing it; or
- c) Prohibiting misrepresentation of the origin of that material, or requiring that modified versions of such material be marked in reasonable ways as different from the original version; or
- d) Limiting the use for publicity purposes of names of licensors or authors of the material; or
- e) Declining to grant rights under trademark law for use of some trade names, trademarks, or service marks; or
- f) Requiring indemnification of licensors and authors of that material by anyone who conveys the material (or modified versions of it) with contractual assumptions of liability to the recipient, for any liability that these contractual assumptions directly impose on those licensors and authors.

All other non-permissive additional terms are considered “further restrictions” within the meaning of section 10. If the Program as you received it, or any part of it, contains a notice stating that it is governed by this License along with a term that is a further restriction, you may remove that term. If a license document contains a further restriction but permits relicensing or conveying under this License, you may add to a covered work material governed by the terms of that license document, provided that the further restriction does not survive such relicensing or conveying.

If you add terms to a covered work in accord with this section, you must place, in the relevant source files, a statement of the additional terms that apply to those files, or a notice indicating where to find the applicable terms.

Additional terms, permissive or non-permissive, may be stated in the form of a separately written license, or stated as exceptions; the above requirements apply either way.

## 8. Termination.

You may not propagate or modify a covered work except as expressly provided under this License. Any attempt otherwise to propagate or modify it is void, and will automatically terminate your rights under this License (including any patent licenses granted under the third paragraph of section 11).

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.



Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, you do not qualify to receive new licenses for the same material under section 10.

#### 9. Acceptance Not Required for Having Copies.

You are not required to accept this License in order to receive or run a copy of the Program. Ancillary propagation of a covered work occurring solely as a consequence of using peer-to-peer transmission to receive a copy likewise does not require acceptance. However, nothing other than this License grants you permission to propagate or modify any covered work. These actions infringe copyright if you do not accept this License. Therefore, by modifying or propagating a covered work, you indicate your acceptance of this License to do so.

#### 10. Automatic Licensing of Downstream Recipients.

Each time you convey a covered work, the recipient automatically receives a license from the original licensors, to run, modify and propagate that work, subject to this License. You are not responsible for enforcing compliance by third parties with this License.

An “entity transaction” is a transaction transferring control of an organization, or substantially all assets of one, or subdividing an organization, or merging organizations. If propagation of a covered work results from an entity transaction, each party to that transaction who receives a copy of the work also receives whatever licenses to the work the party's predecessor in interest had or could give under the previous paragraph, plus a right to possession of the Corresponding Source of the work from the predecessor in interest, if the predecessor has it or can get it with reasonable efforts.

You may not impose any further restrictions on the exercise of the rights granted or affirmed under this License. For example, you may not impose a license fee, royalty, or other charge for exercise of rights granted under this License, and you may not initiate litigation (including a cross-claim or counterclaim in a lawsuit) alleging that any patent claim is infringed by making, using, selling, offering for sale, or importing the Program or any portion of it.

#### 11. Patents.

A “contributor” is a copyright holder who authorizes use under this License of the Program or a work on which the Program is based. The work thus licensed is called the contributor's “contributor version”.

A contributor's “essential patent claims” are all patent claims owned or controlled by the contributor, whether already acquired or hereafter acquired, that would be infringed by some manner, permitted by this License, of making, using, or selling its contributor version, but do not include claims that would be infringed only as a consequence of further modification of the contributor version. For purposes of this definition, “control” includes the right to grant patent sublicenses in a manner consistent with the requirements of this License.



Each contributor grants you a non-exclusive, worldwide, royalty-free patent license under the contributor's essential patent claims, to make, use, sell, offer for sale, import and otherwise run, modify and propagate the contents of its contributor version.

In the following three paragraphs, a “patent license” is any express agreement or commitment, however denominated, not to enforce a patent (such as an express permission to practice a patent or covenant not to sue for patent infringement). To “grant” such a patent license to a party means to make such an agreement or commitment not to enforce a patent against the party.

If you convey a covered work, knowingly relying on a patent license, and the Corresponding Source of the work is not available for anyone to copy, free of charge and under the terms of this License, through a publicly available network server or other readily accessible means, then you must either (1) cause the Corresponding Source to be so available, or (2) arrange to deprive yourself of the benefit of the patent license for this particular work, or (3) arrange, in a manner consistent with the requirements of this License, to extend the patent license to downstream recipients. “Knowingly relying” means you have actual knowledge that, but for the patent license, your conveying the covered work in a country, or your recipient's use of the covered work in a country, would infringe one or more identifiable patents in that country that you have reason to believe are valid.

If, pursuant to or in connection with a single transaction or arrangement, you convey, or propagate by procuring conveyance of, a covered work, and grant a patent license to some of the parties receiving the covered work authorizing them to use, propagate, modify or convey a specific copy of the covered work, then the patent license you grant is automatically extended to all recipients of the covered work and works based on it.

A patent license is “discriminatory” if it does not include within the scope of its coverage, prohibits the exercise of, or is conditioned on the non-exercise of one or more of the rights that are specifically granted under this License. You may not convey a covered work if you are a party to an arrangement with a third party that is in the business of distributing software, under which you make payment to the third party based on the extent of your activity of conveying the work, and under which the third party grants, to any of the parties who would receive the covered work from you, a discriminatory patent license (a) in connection with copies of the covered work conveyed by you (or copies made from those copies), or (b) primarily for and in connection with specific products or compilations that contain the covered work, unless you entered into that arrangement, or that patent license was granted, prior to 28 March 2007.

Nothing in this License shall be construed as excluding or limiting any implied license or other defenses to infringement that may otherwise be available to you under applicable patent law.

## 12. No Surrender of Others' Freedom.

If conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot convey a covered work so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not convey it at all. For example, if you agree to terms that obligate you to collect a royalty for further conveying from those to whom you convey the Program, the only way you could satisfy both those terms and this License would be to refrain entirely from conveying the Program.

## 13. Use with the GNU Affero General Public License.

Notwithstanding any other provision of this License, you have permission to link or combine any covered work with a work licensed under version 3 of the GNU Affero General Public License into a single combined work, and to convey the resulting work. The terms of this License will continue to apply to the part which is the covered work, but the special requirements of the GNU Affero General Public License, section 13, concerning interaction through a network will apply to the combination as such.

#### 14. Revised Versions of this License.

The Free Software Foundation may publish revised and/or new versions of the GNU General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies that a certain numbered version of the GNU General Public License “or any later version” applies to it, you have the option of following the terms and conditions either of that numbered version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of the GNU General Public License, you may choose any version ever published by the Free Software Foundation.

If the Program specifies that a proxy can decide which future versions of the GNU General Public License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Program.

Later license versions may give you additional or different permissions. However, no additional obligations are imposed on any author or copyright holder as a result of your choosing to follow a later version.

#### 15. Disclaimer of Warranty.

THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

#### 16. Limitation of Liability.

IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MODIFIES AND/OR CONVEYS THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

#### 17. Interpretation of Sections 15 and 16.

If the disclaimer of warranty and limitation of liability provided above cannot be given local legal effect according to their terms, reviewing courts shall apply local law that most closely approximates an absolute waiver of all civil liability in connection with the Program, unless a warranty or assumption of liability accompanies a copy of the Program in return for a fee.

## END OF TERMS AND CONDITIONS

LibJpeg8

Version: 8.4.0

Copyright © 1991-2010, Thomas G. Lane, Guido Vollbeding

## LEGAL ISSUES [ from README supplied with source - MM ]

The authors make NO WARRANTY or representation, either express or implied, with respect to this software, its quality, accuracy, merchantability, or fitness for a particular purpose. This software is provided "AS IS", and you, its user, assume the entire risk as to its quality and accuracy.

This software is copyright (C) 1991-2010, Thomas G. Lane, Guido Vollbeding.

All Rights Reserved except as specified below.

Permission is hereby granted to use, copy, modify, and distribute this software (or portions thereof) for any purpose, without fee, subject to these conditions:

- (1) If any part of the source code for this software is distributed, then this README file must be included, with this copyright and no-warranty notice unaltered; and any additions, deletions, or changes to the original files must be clearly indicated in accompanying documentation.
- (2) If only executable code is distributed, then the accompanying documentation must state that "this software is based in part on the work of the Independent JPEG Group".
- (3) Permission for use of this software is granted only if the user accepts full responsibility for any undesirable consequences; the authors accept NO LIABILITY for damages of any kind.

These conditions apply to any software derived from or based on the IJG code, not just to the unmodified library. If you use our work, you ought to acknowledge us.

Permission is NOT granted for the use of any IJG author's name or company name in advertising or publicity relating to this software or products derived from it. This software may be referred to only as "the Independent JPEG Group's software".

We specifically permit and encourage the use of this software as the basis of commercial products, provided that all warranty or liability claims are assumed by the product vendor.

ansi2knr.c is included in this distribution by permission of L. Peter Deutsch, sole proprietor of its copyright holder, Aladdin Enterprises of Menlo Park, CA.

ansi2knr.c is NOT covered by the above copyright and conditions, but instead by the usual distribution terms of the Free Software Foundation; principally, that you must include source code if you redistribute it. (See the file ansi2knr.c for full details.) However, since ansi2knr.c is not needed as part of any program generated from the IJG code, this does not limit you more than the foregoing paragraphs do.

The Unix configuration script "configure" was produced with GNU Autoconf.

It is copyright by the Free Software Foundation but is freely distributable.

The same holds for its supporting scripts (config.guess, config.sub, ltmain.sh). Another support script, install-sh, is copyright by X Consortium but is also freely distributable.

The IJG distribution formerly included code to read and write GIF files. To avoid entanglement with the Unisys LZW patent, GIF reading support has been removed altogether, and the GIF writer has been simplified to produce "uncompressed GIFs". This technique does not use the LZW algorithm; the resulting GIF files are larger than usual, but are readable by all standard GIF decoders.

We are required to state that "The Graphics Interchange Format(c) is the Copyright property of CompuServe Incorporated. GIF(sm) is a Service Mark property of CompuServe Incorporated."

Distributed as part of this product under the Mit License (<https://opensource.org/licenses/MIT>):

cJSON 1.7.11 (Copyright (c) 2009-2017 Dave Gamble and cJSON contributors)

MBED TLS 2.28.0

Version: 2.28.0

Copyright © 2008 - 2021 ARM Limited

Distributed under the Apachev2 License: <http://apache.org/licenses/LICENSE-2.0>

Dex2jar-2.0, Distributed under the Apachev2 License: <http://apache.org/licenses/LICENSE-2.0>

JNA 5.5.0, Distributed under the Apachev2 License: <http://apache.org/licenses/LICENSE-2.0>

Flatbuffers 1.11.0, Distributed under the Apachev2 License: <http://apache.org/licenses/LICENSE-2.0>

Protobuf 3.8.0

Copyright notice:

Copyright 2008 Google Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

\* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

\* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

\* Neither the name of Google Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Code generated by the Protocol Buffer compiler is owned by the owner of the input file used when generating it. This code is not standalone and requires a support library to be linked with it. This support library is itself covered by the above license.

## 7-Zip 19.0

License for use and distribution

~~~~~

7-Zip Copyright (C) 1999-2021 Igor Pavlov.

The licenses for files are:

1) 7z.dll:

- The "GNU LGPL" as main license for most of the code
- The "GNU LGPL" with "unRAR license restriction" for some code
- The "BSD 3-clause License" for some code

2) All other files: the "GNU LGPL".

Redistributions in binary form must reproduce related license information from this file.

Note:

You can use 7-Zip on any computer, including a computer in a commercial organization. You don't need to register or pay for 7-Zip.

GNU LGPL information

-----

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public

License as published by the Free Software Foundation; either  
version 2.1 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful,  
but WITHOUT ANY WARRANTY; without even the implied warranty of  
MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU  
Lesser General Public License for more details.

You can receive a copy of the GNU Lesser General Public License from

<http://www.gnu.org/>

BSD 3-clause License

-----

The "BSD 3-clause License" is used for the code in 7z.dll that implements LZFSE data decompression.  
That code was derived from the code in the "LZFSE compression library" developed by Apple Inc,  
that also uses the "BSD 3-clause License":

----

Copyright (c) 2015-2016, Apple Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the  
following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following  
disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the  
following disclaimer

in the documentation and/or other materials provided with the distribution.

3. Neither the name of the copyright holder(s) nor the names of any contributors may be used to endorse or  
promote products derived

from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY  
EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT

LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR  
PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE

COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL,  
SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES

(INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION)

HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE)

ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

----

unRAR license restriction

-----

The decompression engine for RAR archives was developed using source code of unRAR program.

All copyrights to original unRAR code are owned by Alexander Roshal.

The license for original unRAR code has the following restriction:

The unRAR sources cannot be used to re-create the RAR compression algorithm, which is proprietary. Distribution of modified unRAR sources in separate form or as a part of other software is permitted, provided that it is clearly stated in the documentation and source comments that the code may not be used to develop a RAR (WinRAR) compatible archiver.

OpenJDK8 (from AdoptOpenJDK distribution)

This component is distributed under the Gplv2 license with classpath exception: OpenJDK: GPLv2 + Classpath Exception (java.net) .

Scripts or other files used to produce binaries are distributed under the Apachev2 license.

## Exhibit B - Third-Party Software for Sentinel LDK-EMS

A. The following free software components are used and distributed pursuant to the Apache License, Version 1.1, and are subject to the terms and conditions of said License: (i) Avalon framework 4.1.3 and (ii) logkit-1.0.1.jar. The Apache License, Version 1.1, is located at: <http://www.apache.org/licenses/LICENSE-1.1>.

B. The following free software components are used and distributed pursuant to the Apache License, Version 2.0, and are subject to the terms and conditions of said

License: (i) Spring 4.3.20; (ii) IzPack; (iii) json-lib-2.2.3-jdk15; (iv) EHCache; (v) apache poi-3.13; (vii) ezmorph-1.0.6.jar; (viii) lucene-core-5.5.5.jar; (ix) xercesImpl-2.8.1; Xerces-C++ 3.1.1; (x) xalan-2.6.0; (xi) standalone-compiler.jar; (xii) commons-beanutils-1.7.0; (xiii) commons-collections-3.2; (xiv) commons-lang-2.4; (xv) commons-logging-1.1; (xvi) Quartz 1.6.5; (xvii) Apache Tomcat 9.0.56; (xviii) JCS; (xvii) Log4j; (xx) httpclient-4.5.9.jar; (xxi) httpcore-4.4.11.jar; (xxii) Log4net; (xxiii) commons-fileupload-1.4.jar; (xxiv) commons-beanutils-1.9.4.jar; (xxv) xercesImpl-2.12.0.jar; (xxvi) commons-codec-1.11.jar; (xxvii) commons-collections-3.2.2.jar; (xxviii) xml-apis-1.4.01.jar; and (xxix) jjwt-0.9.1.jar. Said free software components are subject to the following copyright: Copyright © 2012 The Apache Software Foundation. All rights reserved. The Apache License, Version 2.0, is located at: <http://www.apache.org/licenses/LICENSE-2.0>.

C. The following free software components are used and distributed pursuant to the GNU Lesser GPL License 2.1, and are subject to the terms and conditions of said License: (i) XLightWeb; (ii) Hibernate 5.11.1; (iii) DynamicJasper 3.1.1 and (iv) KindEditor 4.1.12 the GNU Lesser GPL License 2.1 is located at: <http://www.gnu.org/licenses/old-licenses/lgpl-2.1.html>.

D. The free software component known as "XStream", version 1.4.19 is used and distributed pursuant to the BSD License for XStream, and is subject to the terms and conditions of said License. The BSD License for XStream is located at: <http://xstream.codehaus.org/license.html>.

E. The free software component known as "Bouncy Castle" is used and distributed pursuant to the terms and conditions of the License located at: <http://www.bouncycastle.org/licence.html>.

F. The free software component known as "Libcurl" is used and distributed pursuant to the terms and conditions of the License located at: <http://curl.haxx.se/legal/licmix.html>.

G. The free software component known as "Libconfig" is used and distributed pursuant to the terms and conditions of the License located at: <http://www.gnu.org/licenses/lgpl.html>.

H. The free software component known as "Liblogger" is used and distributed pursuant to the terms and conditions of the License located at: <http://www.gnu.org/licenses/lgpl-3.0.txt>.



I. The free software component known as "GenX" is used and distributed pursuant to the terms and conditions of the License located at: <http://www.tbray.org/ongoing/genx/COPYING>.

J. The free software components known as "Libexpat", "slf4j-api" and "slf4j-simple" version 1.7.25 are used and distributed pursuant to the MIT License, and is subject to the terms and conditions of said License located at: <http://opensource.org/licenses/MIT>

K. The free software component known as "uthash" is used pursuant to the terms and conditions of the License located at: <http://uthash.sourceforge.net/license.html>.

L. The free software component known as "SpiderMonkey" is used and distributed pursuant to the MPL/GPL/LGPL tri-license, and is subject to the terms and conditions of said Licenses.

M. The free software component known as "OpenSSL" is used and distributed pursuant to the terms and conditions of the License located at: <http://www.openssl.org/source/license.html>.

N. The free software component known as "YUI" is used and distributed pursuant to the BSD License, and is subject to the terms and conditions of said License. The said software component is subject to the following copyright: Copyright © 2010, Yahoo! Inc. All rights reserved. The BSD License for YUI is located at: <http://developer.yahoo.com/yui/license.html>.

O. The free software components known as (i) JasperReports and (ii) JasperBerry\_002 are used and distributed pursuant to the LGPL License, and is subject to the terms and conditions of said License. The LGPL license is available at: <http://www.gnu.org/copyleft/lesser.html>.

P. The free software component known as "Javolution.jar" is used and distributed pursuant to the BSD License for Javolution.jar, and is subject to the terms and conditions of said License. The BSD License for Javolution.jar is located at: <http://javolution.org/LICENSE.txt>.

Q. The free software component known as "jempbox-0.2.0.jar" is used and distributed pursuant to the BSD License for jembox-0.2.0.jar, and is subject to the terms and conditions of said License. The BSD License for jembox-0.2.0.jar is located at: <http://www.jempbox.org/license.html>.

R. The free software component known as "JDOM" is used and distributed pursuant to the JDOM License, and is subject to the terms and conditions of said License. The JDOM License is located at: <http://vmgump.apache.org/gump/public-jars/jdom/jars/LICENSE.txt>.

S. The free software component known as com.ibm.icu - icu4j - 67.1 is used and distributed pursuant to the terms and conditions of the license located at <http://www.unicode.org/copyright.html#License>

T. The free software component known as "Dojo 1.16" is used and distributed pursuant to the terms and conditions of the license located at: <http://o.dojotoolkit.org/license>.

U. The free software component known as "7-zip 4.65" is used and distributed pursuant to the terms and conditions of the license located at: <http://www.7-zip.org/license.txt>.

V. The free software component known as "Curl 7.68.0" is used and distributed pursuant to the terms and conditions of the license located at: <http://curl.haxx.se/docs/copyright.html>

W. The software component known as "JRE 1.8" is used and distributed pursuant to the terms and conditions of the Oracle Binary Code License Agreement, located at:

<http://www.oracle.com/technetwork/java/javase/terms/license/index.html>

X. Distributed as part of this product under the Eclipse Public License (<https://www.eclipse.org/legal/epl-v10.html>):

mchange-commons-java-0.2.15.jar ( © 2012-2013 Machinery for Change, Inc)

c3p0-0.9.5.2.jar (©included in the readme's or equivalent)

aspectjweaver-1.8.10.jar (all required information can be found in the readme's or <https://www.eclipse.org/aspectj/> )

Y. OpenJDK8 is distributed under CDDL License and Gplv2 classpath exception license:

<https://oss.oracle.com/licenses/CDDL+GPL-1.1>

Revision 2204-1